

```

ROUTER
ROUTER(config)#int e0/0
ROUTER(config-if)#no ip add 120.25.0.20 255.255.0.0
ROUTER(config-if)#exit4
^
% Invalid input detected at '^' marker.


ROUTER(config-if)#exit
ROUTER(config)#exit
ROUTER#sh i
*Jul 18 08:40:58.308: %SYS-5-CONFIG_I: Configured from console by ila
ROUTER#sh ip int brief
Interface      IP-Address      OK? Method Status
Ethernet0/0    unassigned      YES unset  up
Ethernet0/1    unassigned      YES TFTP   down
Ethernet0/2    unassigned      YES TFTP   down
Ethernet0/3    unassigned      YES TFTP   down
ROUTER#
ROUTER#conf t
Enter configuration commands, one per line. End with CNTL/Z.
ROUTER(config)#int e0/0
ROUTER(config-if)#ip add 120.25.0.10 255.0.0.0
ROUTER(config-if)#no sh
ROUTER(config-if)#exit
ROUTER(config)#exit
ROUTER#
*Jul 18 08:41:34.049: %SYS-5-CONFIG_I: Configured from console by ila
ROUTER#conf t
Enter configuration commands, one per line. End with CNTL/Z.
ROUTER(config)#host SSH
SSH(config)#ip domain-name ssh.com
SSH(config)#crypto key generate rsa modulus 2048
The name for the keys will be: SSH.ssh.com

% The key modulus size is 2048 bits
% Generating 2048 bit RSA keys, keys will be non-exportable
[OK] (elapsed time was 4 seconds)

SSH(config)#
*Jul 18 08:45:23.073: %SSH-5-ENABLED: SSH 1.99 has been enabled
SSH(config)#ip ssh version2
^
% Invalid input detected at '^' marker.

SSH(config)#ip ssh version 2
SSH(config)#username ila privilege 15 secret ila
SSH(config)#line vty 0 4
SSH(config-line)#transport input ssh
SSH(config-line)#login local
SSH(config-line)#

```



ROUTER

```
% Login disabled on line 4, until 'password' is set
% Login disabled on line 5, until 'password' is set
% Login disabled on line 6, until 'password' is set
ROUTER(config-line)#login local
ROUTER(config-line)#exit
ROUTER(config)#exit
ROUTER#sh i
*Jul 18 08:38:09.373: %SYS-5-CONFIG_I: Configured from console by cisco
e
ROUTER#sh ip int brief
Interface      IP-Address      OK? Method Status
Ethernet0/0    120.25.0.20     YES manual up
Ethernet0/1    unassigned      YES TFTP down
Ethernet0/2    unassigned      YES TFTP down
Ethernet0/3    unassigned      YES TFTP down

ROUTER#conf t
Enter configuration commands, one per line. End with CNTL/Z.
ROUTER(config)#int e0/0
ROUTER(config-if)#no ip add 120.25.0.20 255.255.0.0
ROUTER(config-if)#exit
% Invalid input detected at '^' marker.

ROUTER(config-if)#exit
ROUTER(config)#exit
ROUTER#sh i
*Jul 18 08:40:58.308: %SYS-5-CONFIG_I: Configured from console by cisco
ROUTER#sh ip int brief
Interface      IP-Address      OK? Method Status
Ethernet0/0    unassigned      YES unset up
Ethernet0/1    unassigned      YES TFTP down
Ethernet0/2    unassigned      YES TFTP down
Ethernet0/3    unassigned      YES TFTP down

ROUTER#
ROUTER#conf t
Enter configuration commands, one per line. End with CNTL/Z.
ROUTER(config)#int e0/0
ROUTER(config-if)#ip add 120.25.0.10 255.0.0.0
ROUTER(config-if)#no sh
ROUTER(config-if)#exit
ROUTER(config)#exit
ROUTER#
*Jul 18 08:41:34.049: %SYS-5-CONFIG_I: Configured from console by ccna on console
ROUTER#
```

QEMU (Win)

120.25.0.10 - PuTTY

User Access Verification

Username: ccna

14:12 18-07-2026