

# How computers understand single characters

- Computers store characters as numbers. Every character used by a computer corresponds to a unique number, and vice versa. This assignment must include more characters than you might expect. Many of them are invisible to humans, but essential to computers.
- Some of these characters are called whitespaces, while others are named control characters, because their purpose is to control input/output devices.
- An example of a whitespace that is completely invisible to the naked eye is a special code, or a pair of codes (different operating systems may treat this issue differently), which are used to mark the ends of the lines inside text files.







# How computers understand single characters

- People do not see this sign (or these signs), but are able to observe the effect of their application where the lines are broken.
- We can create virtually any number of character-number assignments, but life in a world in which every type of computer uses a different character encoding would not be very convenient. This system has led to a need to introduce a universal and widely accepted standard implemented by (almost) all computers and operating systems all over the world.
- The one named **ASCII** (short for **American Standard Code for Information Interchange**) is the most widely used, and you can assume that nearly all modern devices (like computers, printers, mobile phones, tablets, etc.) use that code.







imran muet

and Exceptions Part 1: Characteristics and Strings vs Computers

## How computers understand single characters

 The code provides space for **256 different** characters, but we are interested only in the first 128. If you want to see how the code is constructed, look at the table below. Click the table to enlarge it. Look at it carefully - there are some interesting facts. Look at the code of the most common character - the space. This is *32*.

**ImranNust** 





imran muet

| Character | Code | Character | Code |   | Character | Code | Character | Code |
|-----------|------|-----------|------|---|-----------|------|-----------|------|
| (NUL)     | 0    | (space)   | 32   |   | @         | 64   |           | 96   |
| (SOH)     | 1    | 1         | 33   |   | А         | 65   | a         | 97   |
| (STX)     | 2    | "         | 34   |   | В         | 66   | b         | 98   |
| (ETX)     | 3    | #         | 35   |   | С         | 67   | С         | 99   |
| (EOT)     | 4    | \$        | 36   | 0 | D         | 68   | d         | 100  |
| (ENQ)     | 5    | 8         | 37   |   | E         | 69   | е         | 101  |
| (ACK)     | 6    | δε        | 38   |   | F         | 70   | f         | 102  |
| (BEL)     | 7    | •         | 39   |   | G         | 71   | g         | 103  |
| (BS)      | 8    | (         | 40   |   | Н         | 72   | h         | 104  |
| (HT)      | 9    | )         | 41   |   | I         | 73   | i         | 105  |
| (LF)      | 10   | *         | 42   |   | J         | 74   | j         | 106  |
| (VT)      | 11   | +         | 43   |   | K         | 75   | k         | 107  |
| (FF)      | 12   | ,         | 44   |   | L         | 76   | 1         | 108  |
| (CR)      | 13   | -         | 45   |   | М         | 77   | m         | 109  |
| (SO)      | 14   |           | 46   |   | N         | 78   | n         | 110  |
| (SI)      | 15   | /         | 47   |   | 0         | 79   | 0         | 111  |
| (DLE)     | 16   | 0         | 48   |   | P         | 80   | р         | 112  |
| (DC1)     | 17   | 1         | 49   |   | Q         | 81   | q         | 113  |
| (DC2)     | 18   | 2         | 50   |   | R         | 82   | r         | 114  |
| (DC3)     | 19   | 3         | 51   |   | S         | 83   | s         | 115  |
| (DC4)     | 20   | 4         | 52   |   | T         | 84   | t         | 116  |
| (NAK)     | 21   | 5         | 53   |   | U         | 85   | u         | 117  |
| (SYN)     | 22   | 6         | 54   |   | V         | 86   | v         | 118  |
| (ETB)     | 23   | 7         | 55   |   | W         | 87   | W         | 119  |
| (CAN)     | 24   | 8         | 56   |   | Х         | 88   | х         | 120  |
| (EM)      | 25   | 9         | 57   |   | Y         | 89   | У         | 121  |
| (SUB)     | 26   | :         | 58   |   | Z         | 90   | Z         | 122  |
| (ESC)     | 27   | ;         | 59   |   | [         | 91   | {         | 123  |
| (FS)      | 28   | <         | 60   |   | \         | 92   | 1         | 124  |
| (GS)      | 29   | =         | 61   | 8 | ]         | 93   | }         | 125  |
| (RS)      | 30   | >         | 62   |   | ^         | 94   | ~         | 126  |
| (US)      | 31   | ?         | 63   |   | _         | 95   |           | 127  |

### **I18N**

 Of course, the Latin alphabet is not sufficient for the whole of mankind. Users of that alphabet are in the minority. It was necessary to come up with something more flexible and capacious than ASCII, something able to make all the software in the world amenable to internationalization, because different languages use completely different alphabets, and sometimes these alphabets are not as simple as the Latin one.







## **118N**



## INTERNATIONALIZATION

- The **software I18N** is a standard in present times. Each program has to be written in a way that enables it to be used all around the world, among different cultures, languages and alphabets.
- A classic form of ASCII code uses eight bits for each sign. Eight bits mean 256 different characters. The first 128 are used for the standard Latin alphabet (both uppercase and lower-case characters). Is it possible to push all the other national characters used around the world into the remaining 128 locations?







- We need a new term now: a **code point**.
- A code point is a number which makes a character. For example, 32 is a code point which makes a space in ASCII encoding. We can say that standard ASCII code consists of 128 code points.
- As standard ASCII occupies 128 out of 256 possible code points, you can only make use of the remaining 128.
- It's not enough for all possible languages, but it may be sufficient for one language, or for a small group of similar languages.
- Can you set the higher half of the code points
  differently for different languages? Yes, you can. Such
  a concept is called a code page.









- A code page is a **standard for using the upper 128 code points to store specific national characters**. For example, there are different code pages for Western Europe and Eastern Europe, Cyrillic and Greek alphabets, Arabic and Hebrew languages, and so on.
- This means that the one and same code point can make different characters when used in different code pages.
- For example, the code point 200 makes Č (a letter used by some Slavic languages) when utilized by the ISO/IEC 8859-2 code page, and makes Ш (a Cyrillic letter) when used by the ISO/IEC 8859-5 code page.
- In consequence, to determine the meaning of a specific code point, you have to know the target code page.
- In other words, the code points derived from the code page concept are ambiguous.





## Unicode

- Code pages helped the computer industry to solve I18N issues for some time, but it soon turned out that they would not be a permanent solution.
- The concept that solved the problem in the long term was Unicode.









## UCS-4

- The Unicode standard says nothing about how to code and store the characters in the memory and files. It only names all available characters and assigns them to planes (a group of characters of similar origin, application, or nature).
- There is more than one standard describing the techniques used to implement Unicode in actual computers and computer storage systems. The most general of them is **UCS-4**.
- The name comes from Universal Character Set.
- UCS-4 uses 32 bits (four bytes) to store each character, and the code is just the Unicode code points' unique number. A file containing UCS-4 encoded text may start with a BOM (byte order mark), an unprintable combination of bits announcing the nature of the file's contents. Some utilities may require it.
- As you can see, UCS-4 is a rather wasteful standard it increases a text's size by four times compared to standard ASCII. Fortunately, there are smarter forms of encoding Unicode texts.







imran muet

UTF-8

- One of the most commonly used is UTF-8.
- The name is derived from Unicode Transformation
  Format.
- The concept is very smart. UTF-8 uses as many bits for each of the code points as it really needs to represent them.







## UTF-8

- For example:
  - all Latin characters (and all standard ASCII characters) occupy eight bits;
  - non-Latin characters occupy 16 bits;
  - CJK (China-Japan-Korea) ideographs occupy 24 bits.
- Due to features of the method used by UTF-8 to store the code points, there is no need to use the BOM, but some of the tools look for it when reading the file, and many editors set it up during the save.
- Python 3 fully supports Unicode and UTF-8:
  - you can use Unicode/UTF-8 encoded characters to name variables and other entities;
  - you can use them during all input and output.

imran muet

• This means that Python3 is completely I18Ned.







## UTF-8

- For example:
  - all Latin characters (and all standard ASCII characters) occupy eight bits;
  - non-Latin characters occupy 16 bits;
  - CJK (China-Japan-Korea) ideographs occupy 24 bits.
- Due to features of the method used by UTF-8 to store the code points, there is no need to use the BOM, but some of the tools look for it when reading the file, and many editors set it up during the save.
- Python 3 fully supports Unicode and UTF-8:
  - you can use Unicode/UTF-8 encoded characters to name variables and other entities;
  - you can use them during all input and output.
- This means that Python3 is completely I18Ned.





