




Insa Saleem
Fatima Jinnah Women
University Rawalpindi

Computer
Science(BSCS)





Table of Contents

ORGANIZATIONAL OVERVIEW	3
MAXIMO INTRODUCTION	5
Services Provided	5
Maximo Modules	6
1. Asset Management	6
2. Work Management	6
3. Service Management	6
4. Contract Management	6
5. Inventory Management.....	6
6. Procurement Management.....	7
MAXIMO SERVICE REQUEST	12
What is a Service Request?	12
Maximo Service Request.....	12
Add and View Record	12
WORK ORDERS	14
Work order tracking application.....	14
ASSETS MODULE	20
What is an Asset?	20
Assets Application.....	20
PREVENTIVE MAINTENANCE	27
What is Preventive Maintenance?.....	27
Master PM Records.....	27
Master PM Application	27
Preventive Maintenance Records	27
Creating Preventive Maintenance Records	32
Procedure	32
PURCHASE MODULE	33
Purchasing Applications	33
Purchase requisition:	34
Purchase Requisitions Tabs.....	34

Purchase Order	36
How to Create a Purchase Order (PO).....	38
Receiving Application	39
Receiving Application Tabs	39
Receiving Materials and Services.....	39
Invoices Application	40
Required Invoice Information	40
Invoice Types	40
Accessing the Invoices Application.....	40
Invoices Application Tabs	40
Inventory application	42
1. Item Master	43
MAXIMO ADMINISTRATION.....	46
1. Sets Application	46
Types of Sets	46
2. Organizations Application.....	47
3. Calendar Application	48

SOFTWARES COVERING THE ENTIRE ORGANIZATION



ORGANIZATIONAL OVERVIEW

At Attock Refinery Limited (ARL), different software systems are used to manage the organization's daily operations. The main enterprise systems include:

1. **Maximo**
2. **Oracle Financial**
3. **HRMS**

In addition to these systems, ARL also uses several in-house developed applications, such as the Appraisal System, QCL, and Fuel Management System (FMS).

MAXIMO

Maximo is mainly used at ARL for managing plant maintenance, inventory, and procurement activities. Maintenance-related requests, such as reporting a problem with a valve, gauge, or other equipment, can be handled through Maximo. It is also used to manage purchase records, vendor invoices, and inventory information.

ORACLE FINANCIAL

Oracle Financial is used to manage the financial activities of the organization. Its main modules include Cash Management, Accounts Payable, Accounts Receivable, General Ledger, and Fixed Assets.

HRMS

The Human Resource Management System (HRMS) is used to maintain employee-related information. It stores details such as employee information, departments, and salary records.

SYSTEM INTEGRATION

1. Maximo and Oracle Financial:

Invoice and purchase order information from Maximo is transferred to the Accounts Payable module of Oracle Financial.

2. Vendor and Employee Data:

Information about vendors and employees is available from Oracle Financial and can be accessed in Maximo when required.

3. Inventory and General Ledger:

Inventory transactions such as receipts, issues, and transfers are connected with the General Ledger in Oracle Financial.

4. Maximo and HRMS:

Maximo is connected with HRMS to retrieve user and employee-related information when needed.

MAXIMO INTRODUCTION


MAXIMO INTRODUCTION

IBM Maximo Asset Management is an enterprise asset management system used to manage and maintain an organization's assets. It provides a central platform for handling maintenance activities, inventory, procurement, work orders, and other related operations.

Why Maximo?

Maximo helps organizations manage their assets and maintenance activities in a more organized way. Some of its main benefits include:

- Reducing maintenance costs and operational risks.
- Improving the reliability and useful life of assets.
- Providing better control and visibility of maintenance activities.
- Increasing the efficiency and productivity of maintenance teams.
- Supporting preventive maintenance and reducing unexpected equipment failures.
- Improving the management of inventory, purchasing, and other resources.



Services Provided

Maximo provides a range of services to support the organization's maintenance and asset management activities. These include:

- A stable and secure environment for managing Maximo operations.
- Access to the system through a web browser.

- Help desk and technical support.
- System administration, maintenance, and upgrades.
- Separate development or training environments for testing and learning.
- Learning resources for users to understand and work with Maximo.
- Support for system integration, data migration, and mobile solutions where required.
- Maintenance request and service management through web-based options.

Overall, Maximo helps organizations manage equipment history, maintenance schedules, preventive maintenance, work orders, labor, expenses, procurement, inventory, and reporting. This allows maintenance work to be better organized while helping reduce downtime and unnecessary costs.

Maximo Modules

Maximo organizes its applications into different modules. Each module contains applications that are related to a particular area of work. For example, purchasing-related applications are grouped under the Purchasing area, while work order activities are handled through Work Management applications.

The main Maximo management modules discussed in this report are:

1. Asset Management

Used to maintain information about assets and locations throughout their complete life cycle. It helps keep track of asset details, maintenance history, status, and related information.

2. Work Management

Used to manage both planned and unplanned maintenance work, starting from the initial request and continuing until the work is completed.

3. Service Management

Used to manage service requests and service-related activities. It also supports service level agreements (SLAs) and monitoring of service delivery.

4. Contract Management

Used to manage different types of contracts, including purchase, lease, rental, warranty, and labor-related contracts.

5. Inventory Management

Used to manage spare parts, tools, and other inventory items. It helps users keep track of stock levels, item usage, locations, and availability.

6. Procurement Management

Used to manage purchasing activities, including requests for materials or services, purchasing from vendors, receiving items, and related procurement processes.

MAXIMO APPLICATIONS AND FUNCTIONS

Analytics

Module	Application	Function
Analytics		Applications used to view reports and monitor system performance.
	Report Viewer	Used to run, view, and schedule standard or customized reports.
	KPI Viewer	Used to monitor Key Performance Indicators against organizational goals.
	Business Analysis	Used to analyze trends, performance, and operational data.

Assets

Module	Application	Function
Assets		Applications used to manage assets, locations, and related information.
	Assets	Used to create and maintain asset records, including location, vendor, status, and maintenance details.
	Asset Templates	Used to create standard templates for asset specifications, safety plans, and preventive maintenance.
	Locations	Used to create locations and track the assets associated with them.
	Meters	Used to define meters for monitoring asset and location performance.
	Relationships	Used to manage relationships between different assets.
	Meter Groups	Used to group meters and apply them to assets or locations.
	Condition Monitoring	Used to monitor asset conditions and define limits that may require maintenance action.
	Failure Codes	Used to define problems, causes, and remedies related to asset failures.
	Assets (Oil)	Used for asset management according to Oil & Gas requirements.
	Location Profile (Oil)	Used to manage operational profiles for Oil & Gas locations.
	Locations (Oil)	Used to manage locations and their hierarchy in Oil & Gas operations.

Inventory

Module	Application	Function
Inventory		Applications used to manage items, tools, stock, and inventory movement.
	Item Master	Used to define inventory items and add them to storeroom stock.
	Service Items	Used to define services required for purchasing or work orders.
	Tools	Used to define and manage tools available in storerooms.
	Stocked Tools	Used to manage tools kept as inventory.
	Inventory	Used to manage stock levels, item usage, reordering, and rotating assets.
	Issues and Transfers	Used to issue stock and transfer items between storerooms.
	Inventory Usage	Used to track the consumption and movement of inventory items.
	Condition Codes	Used to define the condition of inventory items.
	Storerooms	Used to manage storeroom locations and their stocked items.
	Item Master (Oil)	Used to manage items and materials specific to Oil & Gas operations.
	Inventory Inspection	Used to record inspection and quality checks for inventory items.

Planning

Module	Application	Function
Planning		Applications used to plan maintenance work and related activities.
	Job Plans	Used to define how a job will be performed and the resources required.
	Routes	Used to define assets or locations included in inspection and maintenance routes.
	Safety	Used to include safety requirements, hazards, precautions, and Lock Out/Tag Out procedures in work planning.
	Asset List (Oil)	Used to group assets for maintenance planning in Oil & Gas operations.
	Condition for Work (Oil)	Used to record the conditions that must be met before work can begin.
	Regulatory Compliance (Oil)	Used to record and monitor compliance with required regulations and standards.
	Prioritization Matrix (Oil)	Used to prioritize work based on risk, asset criticality, and other factors.

	Job Plans (Oil)	Used to create job plans with Oil & Gas-specific requirements and safety procedures.
	Benefits and Losses (Oil)	Used to record financial and operational benefits or losses related to planned work.
	Routes (Oil)	Used to manage inspection and maintenance routes for petroleum operations.
	Manage Inspection Forms	Used to create and manage inspection forms and checklists.
	Standard Actions (Oil)	Used to define standard corrective or preventive actions.
	Standard Action Groups (Oil)	Used to group standard actions for easier assignment and management.

Preventive Maintenance

Module	Application	Function
Preventive Maintenance		Applications used to plan and manage preventive maintenance activities.
	Preventive Maintenance	Used to schedule regular maintenance and inspections for assets and locations.
	Master PM	Used to create general preventive maintenance templates.
	Preventive Maintenance (Oil)	Used to manage preventive maintenance schedules for Oil & Gas assets.

Purchasing

Module	Application	Function
Purchasing		Applications used to manage purchasing and supplier-related activities.
	Purchase Requisition	Used to request materials or services for purchase.
	Purchase Order Local	Used to create and process purchase orders for local suppliers.
	Receiving	Used to record received materials and services.
	Inventory Usage	Used to record material consumption related to purchasing and work orders.
	Invoices	Used to record invoices and match them with purchase orders and receipts.
	Request for Quotations	Used to request and manage quotations from vendors.
	Companies	Used to maintain information about vendors, manufacturers, and other companies.
	Company Master	Used to maintain companies within a shared company set.
	Terms and Conditions	Used to manage terms and conditions for purchasing and contracts.

	Purchase Requisitions (Oil)	Used to manage purchase requisitions according to Oil & Gas requirements.
	Purchase Orders (Oil)	Used to manage purchase orders for Oil & Gas equipment and suppliers.
	Contractors	Used to maintain contractor information and related details.
	Purchase Orders Foreign	Used to process purchase orders for international suppliers.
	Request for Quotations (Foreign)	Used to manage quotation requests from international suppliers.
	Request for Quotations (CS)	Used to manage customized quotation requests.
	Inventory Receipt (Custom)	Used to record the receipt of specialized inventory items.

Safety and Quality Management

Module	Application	Function
Safety and Quality Management		Applications used to manage safety, quality, and compliance activities.
	Certifications (Oil)	Used to track safety and operational certifications for employees and equipment.
	Audit and Survey (Oil)	Used to manage safety audits, environmental surveys, and field assessments.
	Service Requests (Oil)	Used to handle service requests related to health, safety, and quality issues.
	Ticket Templates (Oil)	Used to create standard templates for safety-related tickets.

Self Service

Module	Application	Function
Self Service		Applications that allow users to submit and track their own requests.
	Desktop Requisitions	Used to create, view, and submit material or service requisitions.
	Service Requests	Used to search solutions, create service requests, and view submitted requests.
	View Requisition WF	Used to check the approval status and workflow of requisitions.
	Submit a Service Request	Used by users to quickly submit a new service issue.
	Create Material Requisition (Custom)	Used to request specific materials directly from available stock.

Work Orders

Module	Application	Function
Work Orders		Applications used to manage work orders, assignments, labor, and maintenance activities.
	Work Order Tracking	Used to create, update, and track work orders throughout their lifecycle.
	Labor Reporting	Used to record hours worked by employees or contractors.
	Quick Reporting	Used to quickly report completed work or small jobs.
	Activities and Tasks	Used to divide work orders into smaller tasks and manage them.
	Assignment Manager	Used to assign urgent work and plan upcoming work requirements.
	Service Requests	Used to view service requests and convert them into work orders.
	Work Order Tracking (Oil)	Used to manage work orders with requirements specific to Oil & Gas operations.
	Action Tracking (Oil)	Used to monitor corrective actions and safety-related activities.
	Drilling and Completion (Oil)	Used to manage work orders related to drilling and well-completion activities.
	Quick Reporting (Oil)	Used by field technicians to quickly report work in Oil & Gas operations.
	Service Requests (Oil)	Used to record service requests related to petroleum plant operations.
	Meter Reading Interface	Used to enter and process meter readings for assets.
	Work Centers	Used to provide role-based dashboards for technicians, supervisors, and inspectors.

MAXIMO SERVICE REQUEST

MAXIMO SERVICE REQUEST

What is a Service Request?

A **Service Request** is used to report or request a service related to an asset, location, or other organizational need. In Maximo, users can submit a request by providing the required details, selecting the relevant asset or location, and setting its priority. The request can then be tracked until the required work is completed.

Maximo Service Request

Maximo provides an easy way for users to create and track service requests. When a request is submitted, the system records the requester and the details of the issue. The request can then be reviewed, processed, and converted into further maintenance work when required.

Add and View Record

The following steps are used to create and manage a service request:

- The user logs into Maximo and creates a new service request.
- The **Reported By** field is automatically filled with the user's information.
- The user enters a short **Summary** and a detailed description of the request.
- The required **Asset** is selected from the available asset list.
- The related **Location** is automatically displayed based on the selected asset.
- The user selects the required **Priority** for the request.
- The request is submitted for further processing.
- Previously created service requests can be viewed from the list.
- Users can also check the current status of their submitted requests.

Home

View Service Requests

Find Navigation Item

Go To Applications

My Recent Applications

Administration

Analytics

Assets

Change

Contracts

Financial

IT Infrastructure

Integration

Inventory

Management of Change

Operations (Oit)

Planning

Preventive Maintenance

Purchasing

Release

Safety and Quality Manage...

Security

Self Service

Service Desk

Service Level

System Configuration

Task Management

Work Orders

Create Service Request

Reported By: INTERN

Phone:

E-mail:

Affected User: INTERN

Asset:

Location:

Configuration Item:

Reported Priority:

Reported Date: 8/10/26 2:01 PM

Request Description

Please enter a summary and a more detailed description of your Service Request.

Summary:

Details:

Classify

Click the detail menu to classify your Service Request.

Classification:

Class Description:

Attachments

Document

Description

There are no rows to display.

Attach Files

Attach Web Page

Home

View Service Requests

Find Navigation Item

Go To Applications

My Recent Applications

Administration

Analytics

Assets

Change

Contracts

Financial

IT Infrastructure

Integration

Inventory

Management of Change

Operations (Oit)

Planning

Preventive Maintenance

Purchasing

Release

Safety and Quality Manage...

Security

Self Service

Service Desk

Service Level

System Configuration

Task Management

Work Orders

Create Service Request

Search for Service Request

Service Request:

Status:

Asset:

Location:

Configuration Item:

Reported Date From:

Reported Date To:

Summary:

Affected User:

Find

Reset

Advanced Search

Save Query

1 - 10 of 56

View Service Requests

Service Request	Summary	Description	Status	Asset	Location	Configuration Item	Reported Date	Affected User
334305	Intern SR		APPR		WRK-LN 7-QTR2		10/23/24 10:09 AM	INTERN
334312	SR inhouse		APPR	HB1-P 310B-M HBU-I			10/23/24 10:54 AM	INTERN
334367	power plant maintenance		NEW	PP-T1 202A	PP		7/23/25 9:46 AM	INTERN
334462	TEST		NEW		WRK-LN 7-QTR2		6/29/26 11:40 AM	INTERN
334373			NEW	CAS-F-104A	CAS		7/21/25 3:00 PM	INTERN
334375			NEW	HB1-P 310B-M HBU-I			7/21/25 3:21 PM	INTERN
334377	TEST-HASSAAN		NEW	HB1-P 310B-M HBU-I			7/21/25 3:22 PM	INTERN
334339	sr today		RESOLVED	HB1-P 310B-M HBU-I			11/13/24 9:29 AM	INTERN
334300			NEW	HB1-P 310B-M HBU-I			10/22/24 8:56 AM	INTERN
334301			APPR	HB1-P 310B-M HBU-I			10/22/24 9:56 AM	INTERN

WORK ORDERS

Work Order Module

Work orders are the core of maintenance management. A work order specifies a particular task to be accomplished, and the labor, materials, services, and tools needed to complete the work. The Work Orders Module consists of the following applications:

1. **Work Order Tracking:** Used to perform every function related to processing work orders.
2. **Labor Reporting:** Used to report hours worked by labor (employees) or contractors. You can enter hours worked by labor ("timecard" reporting), contract/vendor, ticket, or work order.
3. **Quick Reporting:** Used to report work on open work orders and small jobs without preexisting work orders, report actuals, equipment downtime, failure reporting, and meter readings.
4. **Activities and Tasks:** Used to define, break down, and manage sub-tasks assigned under a work order.
5. **Assignment Manager:** Used to dispatch urgent work and schedule future work requirements.
6. **Service Requests:** Used to create records of customer calls or emails requesting service, and convert customer service requests into actionable work orders.
7. **Work Order Tracking (Oil):** Specialized work order tracking application tailored with safety permits and Oil & Gas domain parameters.
8. **Action Tracking (Oil):** Used to monitor progress on corrective actions and safety compliance items.
9. **Drilling and Completion (Oil):** Used to manage work orders specific to drilling and well-completion activities.
10. **Quick Reporting (Oil):** Fast reporting tool customized for field technicians operating in Oil & Gas environments.
11. **Service Requests (Oil):** Specialized request logging for petroleum plant operations.
12. **Meter Reading Interface:** Used to input and process manual or automated meter readings on assets.
13. **Work Centers:** Role-based dashboards for technicians, supervisors, and inspectors to streamline daily workflow tasks.

Work order tracking application

You use the Work Order Tracking application to create, view, and manage work orders. This application contains all of the functions that Maximo includes for processing work orders. To access the Work Order Tracking, click the application link on your Start Center, or select Work Orders > Work Order Tracking from the Go To menu. [The Work Order Tracking application contains the following tabs:](#)

- List:** Displays a list to search Maximo for work order records.

Work Order	Description	Location	Asset	Status	Imp. Dept/Section	Contractor	Reported Date	Estimated Amount
49645	SHIFTING OF FIBER OPTIC CABLE AT ELLIOTT CLUB	ELL-CLUB		COMP	C&MMIT		4/20/11 2:45 PM	7,000.00
49675	Re-Routing of Fiber Optic Cable at Fair Price Shop	HR-DEPT		APPR	C&MMIT	338	5/16/11 3:16 PM	10,000.00
50558	Provision of Blinds at misc locations at reformer	REF		CAN	MAINT/PM-I		6/2/11 1:37 PM	0.00
56241				CAN	MAINT/PM-I		8/31/11 12:00 AM	0.00
55798	Monthly PM Schedule for Hot Pumps (A-Series) at HBU-II			CAN	MAINT/PM-I		8/24/11 12:00 AM	0.00
57703	Monthly PM Schedule for Hot Pumps (A-Series) at HBU-II			CAN	MAINT/PM-I		9/7/11 12:00 AM	0.00
62027	JP Filters #1 & 3 packing with calcium chloride	LUM		COMP	OPS/LUM	334	1/10/12 2:52 PM	6,000.00
59292	Miscellaneous Shutdown jobs	LUM		COMP	OPS/LUM	334	10/21/11 3:30 PM	9,600.00
62589	pulling back the cables at LPG area	OM-I		WAPPR	OPS/OM-I		1/26/12 9:48 AM	1,104.00
62590	installing & dismental foam lines 9-7	REF-TK	RT-TK 7	WAPPR	OPS/OM-I		1/26/12 9:49 AM	0.00
62448	IEE Study for Power Plant Expansion Project	P&D-DEPT		APPR	P&D/P&D	5312	1/23/12 10:02 AM	400,000.00
59405	JP-4 Filter#1 Packing & Lummus/Merox Area Cleaning	LUM		COMP	OPS/LUM	334	10/27/11 3:08 PM	3,900.00
60378	Repairing of Humak paking Area	HMK-PRK		CAN	MAINT/CIVIL	334	11/25/11 8:25 AM	129,250.00
63852	Gravel shifting and spreading at Reformer	REF		APPR	OPS/REF		2/28/12 1:01 PM	2,000.00
65845	tube light change	CALIBRTN-FCLTY		WAPPR	OPS/OM-II		4/25/12 10:16 AM	0.00
65781	Maintenance of HP Printers	IT-DEPT		WAPPR	C&MMIT	2687	4/23/12 8:44 AM	7,500.00
65844	REPAIR FOR CIGARETTES LIGHTER	CALIBRTN-FCLTY		WAPPR	OPS/OM-II		4/25/12 10:17 AM	0.00

- Work Order:** Allows to create, view, or modify work orders, view identifiers for an applied job plan and safety plan, view PM and scheduling information. If the work order is a follow-up work order, you can view the identifier of its originating work order. You also can identify the failure hierarchy for the work asset.

Work Order: 57703 Monthly PM Schedule for Hot Pumps (A-Series) at HBU-II

Location: [Field] Asset: [Field] Status: [Field]

GL Account: [Field] Work Type: PM Parent WO: [Field]

Implementing Department / Section: MAINT/PM-I

Originating Department / Section: [Field]

Area: [Field] Contractor: [Field] Contractor Name: [Field]

Work Rate / Contract: [Field] Repair Facility Site: [Field] Repair Facility: [Field]

Job Details

Meter Reading (Projected): [Field] Meter Reading (Latest WO Generated): [Field] Actual Meter Reading: [Field]

Asset Details

Asset Up? [Field] Warranties Exist? [Field] SLA Applied? [Field]

Priority

Asset Location Priority: [Field] Priority Justification: [Field] Risk Assessment: [Field]

Budget

M&R Budget? [Field] Budget Type: [Field] Budget Code: [Field]

Check Contingency Availability: [Field] Budget Contingency Utilization? [Field] Stock Item Withdrawal: [Field]

WO Cost Details

Estimated Amount: 0.00 Actual Amount (Services & Material): 0.00 Actual Amount Paid by Finance: [Field]

- Plans:** Allows to enter, view, or modify information on work orders in a hierarchy, and to enter, view, modify, or delete information about planned job tasks, labor, materials, services, and tools.

Work Order Tracking

Find Work Order: [Search]

Find Navigation Item: [Search]

Go To Applications: [Link]

Available Queries: [Link]

All Records: [Link]

All Bookmarks: [Link]

All Work Orders: [Link]

All section open work orders with paid...: [Link]

Asset: [Link]

Maint. Approved Work Orders (Contra...: [Link]

Contractor unclosed work orders: [Link]

Contractor work orders with respect to...: [Link]

Common Actions

New Work Order: [Link]

Save Work Order: [Link]

Clear Changes: [Link]

Create Report: [Link]

More Actions

Workflow: [Link]

View SLAs: [Link]

Change Work Order Options: [Link]

Create: [Link]

View: [Link]

Apply Route: [Link]

Run Billing Interface: [Link]

Maintenance Downstream Interface: [Link]

Work Order: 57703 Monthly PM Schedule for Hot Pumps (A-Series) at HBU-II Site: ARLPWD Status: CAN

Parent WO: [Link]

Children of Work Order 57703

Sequence	Record	Record Class	Summary	Location	Asset	Status
459267	WORKORDER	Entered by automation		HBU-I	HBI-P 312A-I	WAPPR
1	57704	WORKORDER	Monthly Maintenance Job Plan for Hot Centre	HBU-II	HBI-P 105A	CAN
2	57705	WORKORDER	Monthly Maintenance Job Plan for Hot Centre	HBU-II	HBI-P 106A	CAN
3	57706	WORKORDER	Monthly Maintenance Job Plan for Hot Centre	HBU-II	HBI-P 107A	CAN
4	57707	WORKORDER	Monthly Maintenance Job Plan for Hot Centre	HBU-II	HBI-P 108A	CAN

Select Assets: [Link] Select Locations: [Link] Select Work Orders: [Link] New Row: [Link]

Tasks for Work Order 57703

Sequence	Task	Summary	Estimated Duration	Status	Owner	Owner Group
1	Clean suction strainer		0:30	WSCH		
2	Cleaning of Pump body of pumps		0:21	WSCH		
3	Mechanical seal flushing		0:10	WSCH		
4	Cooler Cleaning of Hot Pumps		0:10	WSCH		

Labor Materials Services Tools

Labor: [Link] Filter: [Link] 0 - 0 of 0

Assignments: Used to assign work tasks to specific labor or crews, track target and scheduled start/finish dates, manage craft/skill requirements, and monitor assignment completion status.

Work Order Tracking

Find Work Order: [Search]

Find Navigation Item: [Search]

Go To Applications: [Link]

Available Queries: [Link]

All Records: [Link]

All Bookmarks: [Link]

All Work Orders: [Link]

All section open work orders with paid...: [Link]

Asset: [Link]

Maint. Approved Work Orders (Contra...: [Link]

Contractor unclosed work orders: [Link]

Contractor work orders with respect to...: [Link]

Common Actions

New Work Order: [Link]

Save Work Order: [Link]

Clear Changes: [Link]

Create Report: [Link]

More Actions

Workflow: [Link]

View SLAs: [Link]

Change Work Order Options: [Link]

Create: [Link]

View: [Link]

Apply Route: [Link]

Run Billing Interface: [Link]

Maintenance Downstream Interface: [Link]

Work Order: 57703 Monthly PM Schedule for Hot Pumps (A-Series) at HBU-II Site: ARLPWD Status: CAN

Parent WO: [Link]

Scheduled Start: [Link] Target Start: 9/7/11 12:00 AM

Scheduled Finish: [Link] Target Finish: 9/7/11 1:00 AM

Assignments

Task	Description	Crew Type	Craft	Skill Level	Labor	Crew	Scheduled Start	Hours	Status
There are no rows to display.									

Available Crew: [Link] Available Labor: [Link] Complete Assignment: [Link] New Row: [Link]

Related Records: Allows to add, view, or delete related ticket and work order records.

Work Order Tracking

Find Work Order: [Search]

Find Navigation Item: [Search]

Go To Applications: [Link]

Available Queries: [Link]

All Records: [Link]

All Bookmarks: [Link]

All Work Orders: [Link]

All section open work orders with paid...: [Link]

Asset: [Link]

Maint. Approved Work Orders (Contra...: [Link]

Contractor unclosed work orders: [Link]

Contractor work orders with respect to...: [Link]

Common Actions

New Work Order: [Link]

Save Work Order: [Link]

Clear Changes: [Link]

Create Report: [Link]

More Actions

Workflow: [Link]

View SLAs: [Link]

Change Work Order Options: [Link]

Create: [Link]

View: [Link]

Apply Route: [Link]

Run Billing Interface: [Link]

Maintenance Downstream Interface: [Link]

Work Order: 57703 Monthly PM Schedule for Hot Pumps (A-Series) at HBU-II Site: ARLPWD Status: CAN

section...: [Link]

Related Invoices

Invoice	Description	Status	Entered Date	Invoice Total
There are no rows to display.				

Meter Reading Interface

Batched	Description	Status	Interface Processing Month	Processing Date	Updated By
There are no rows to display.					

Related Work Orders

Work Order	Description	Class	Status	Relationship
There are no rows to display.				

Select Work Orders: [Link] New Row: [Link]

Related Tickets

Related Record Key	Description	Class	Status	Relationship
There are no rows to display.				

Select Tickets: [Link] New Row: [Link]

Actuals: Used to view, record, and track the actual resources consumed for the work order, including labor hours, materials used, outside services rendered, and tools utilized during job execution.

Work Order Tracking

Find Work Order:

Find Navigation Item:

Go To Applications

Available Queries

All Records

All Bookmarks

All Work Orders

All section open work orders with paid...

Asset

Maint. Approved Work Orders (Contra...

Contractor unclosed work orders

Contractor work orders with respect to...

Common Actions

New Work Order

Save Work Order

Clear Changes

Create Report

More Actions

Workflow

View SLAs

Change Work Order Options

Create

View

Apply Route

Run Billing Interface

Work Order: 57703 Monthly PM Schedule for Hot Pumps (A-Series) at HBU-II Site: ARLPWD Status: CAN

Parent WO: >>

Children of Work Order 57703 Filter > 1 - 5 of 5

Filter > 1 - 4 of 4

Sequence	Task	Summary	Estimated Duration	Status
1	Clean suction strainer		0:30	WSCH
2	Cleaning of Pump body of pumps.		0:21	WSCH
3	Mechanical seal flushing.		0:10	WSCH
4	Cooler Cleaning of Hot Pumps		0:10	WSCH

Labor Materials Services Tools

Labor Filter > 0 - 0 of 0

Task	Labor Name	Approved?	Start Date	Start Time	End Time	Regular Hours	Rate
There are no rows to display.							

Enter Time By Crew Select Labor Select Planned Labor New Row

Safety Plan: Used to view, manage, and associate safety procedures with the work order, including potential hazards, safety precautions, hazardous materials, and Lock Out/Tag Out (LOTO) requirements to ensure safe execution of maintenance tasks.

Work Order Tracking

Find Work Order:

Find Navigation Item:

Go To Applications

Available Queries

All Records

All Bookmarks

All Work Orders

All section open work orders with paid...

Asset

Maint. Approved Work Orders (Contra...

Contractor unclosed work orders

Contractor work orders with respect to...

Common Actions

New Work Order

Save Work Order

Clear Changes

Create Report

More Actions

Workflow

View SLAs

Change Work Order Options

Create

View

Apply Route

Run Billing Interface

Work Order: 57703 Monthly PM Schedule for Hot Pumps (A-Series) at HBU-II Site: ARLPWD Status: CAN

Hazards and Precautions Hazardous Materials Lock Out/Tag Out


Hazards Filter > 0 - 0 of 0

Hazard	Hazard Description	Hazard Type	Related Location	Related Asset
There are no rows to display.				


Precautions Filter > 0 - 0 of 0

Precaution	Description
There are no rows to display.	


Log: Used to record, view, and track historical notes, work progress updates (Work Log), and outgoing or incoming communications (Communication Log) related to the work order.



Failure Reporting: Used to record, view, and analyze asset failure details, including failure classes, failure codes, problem-cause-remedy hierarchies, and specific remarks to track equipment reliability and breakdown causes.



Specifications: Used to define and view technical specifications, attributes, classifications, and class descriptions associated with the work order or its assets.



Service Address: Used to view and manage physical location details, geographic coordinates (latitude and longitude), street addresses, and routing directions associated with the work order.

Work Order Tracking

Find Work Order

Find Navigation Item

Go To Applications

Available Queries

All Records

All Bookmarks

All Work Orders

All section open work orders with paid...

Asset

Maint. Approved Work Orders (Contra...

Contractor unclosed work orders

Contractor work orders with respect to...

Common Actions

New Work Order

Save Work Order

Clear Changes

Create Report

More Actions

Workflow

View SLAs

Change Work Order Options

Create

View

Apply Route

Run Billing Interface

List View

Work Order

Plans

Assignments

Related Records

Actuals

Safety Plan

Log

Failure Reporting

Specifications

Service Address

Inspection Summary

Work Order: 57703

Monthly PM Schedule for Hot Pumps (A-Series) at HBU-II

Organization: ARL

Site: ARLPWD

Address Information

Service Address

Latitude(Y)

Longitude(X)

Reference Point

Directions

Formatted Address

Street Address

Address Line 2

Address Line 3

City

Region/District

County

State/Province

Zip/Postal Code

Country

GEO Code

Time Zone

Inspection Summary: Used to view, generate, and review inspection results and summary reports linked to the work order.

Work Order Tracking

Find Work Order

Find Navigation Item

Go To Applications

Available Queries

All Records

All Bookmarks

All Work Orders

All section open work orders with paid...

Asset

Maint. Approved Work Orders (Contra...

Contractor unclosed work orders

Contractor work orders with respect to...

Common Actions

New Work Order

Save Work Order

Clear Changes

Create Report

More Actions

Workflow

View SLAs

Change Work Order Options

Create

View

Apply Route

Run Billing Interface

List View

Work Order

Plans

Assignments

Related Records

Actuals

Safety Plan

Log

Failure Reporting

Specifications

Service Address

Inspection Summary

Generate Inspection Summary

WONUM: 57703

No Inspection result found against current Work Order

Inspsummary

ASSETS MODULE

ASSETS MODULE

What is an Asset?

An **asset** is any equipment, machinery, facility, or technology that an organization owns or leases and needs to manage and maintain through Maximo.

Examples of assets include:

- **Production:** Motors, pumps, winches, presses, etc.
- **Facilities:** Plumbing systems, lighting, fire extinguishers, etc.
- **Fleet:** Forklifts, trucks, buses, trains, etc.
- **Technology:** Computers, routers, hubs, servers, etc.


Assets Application

The **Assets** application is used to maintain records of assets and manage them throughout their life cycle. It keeps important information about an asset, including its status, location, life-to-date information, spare parts, and related asset structure.

The Assets application contains the following main tabs:


- **List:** Used to search and view existing asset records.
- **Asset:** Used to create, update, and maintain asset information.
- **Spare Parts:** Used to manage the spare parts and sub-parts associated with an asset.
- **Safety:** Used to maintain safety-related information for an asset.
- **Meters:** Used to enter and view meter readings and life-to-date meter information.
- **Specifications:** Used to maintain the specifications of an asset according to its classification.

List: Used to search, filter, and view existing asset records along with key summary details like asset ID, description, location, type, parent asset, and site.



Asset	Description	Location	Asset Type	Parent	Rotating Item	Site
PP-TI-202A	Water Tube Boiler	PP	INSTRUMENTATION PP-ENG 200			ARLPHWD
PP-TI-202	Temperature Gauge / Lubr Oil Cooler Outlet (L.T) PP-E 202	PP	INSTRUMENTATION PP-E 202			ARLPHWD
PP-TI-206	Temperature Gauge / H.T Cooler Outlet (L.T)	PP	INSTRUMENTATION PP-ENG 200			ARLPHWD
PP-TI-207	Temperature Gauge / L.O Cooler Inlet (L.T) PP-E 202	PP	INSTRUMENTATION PP-E 202			ARLPHWD
PP-TI-208	Temperature Gauge / H.T Cooler Inlet (L.T) PP-E 204	PP	INSTRUMENTATION PP-E 204			ARLPHWD
PP-TI-210	Temperature Gauge / H.T Water Engine Inlet	PP	INSTRUMENTATION PP-ENG 200			ARLPHWD
PP-TI-211	Temperature Element / Air Cooler Inlet (L.T)	PP	INSTRUMENTATION PP-ENG 200			ARLPHWD
PP-TI-211A	Temperature Gauge / H.T Water A1 Cylinder Outlet	PP	INSTRUMENTATION PP-ENG 200			ARLPHWD
PP-TI-211B	Temperature Gauge / H.T Water A2 Cylinder Outlet	PP	INSTRUMENTATION PP-ENG 200			ARLPHWD
HS2-TI-22	Temperature Gauge / E-101 Shell Inlet	HB-U-II	INSTRUMENTATION HSD-E 101			ARLPHWD
HS2-TI-23	Temperature Gauge / E-101 Shell Outlet	HB-U-II	INSTRUMENTATION HSD-E 101			ARLPHWD
HS2-TI-24	Temperature Gauge / E-107 Shell Inlet	HB-U-II	INSTRUMENTATION HSD-E 107			ARLPHWD
HS2-TI-25	Temperature Gauge / E-107 Shell Outlet	HB-U-II	INSTRUMENTATION HSD-E 107			ARLPHWD
HS2-E-116	Flow Element / Fuel Oil to Heater Burner H-101	HB-U-II	INSTRUMENTATION HSD-E 101			ARLPHWD
HS1-LV-301	Valve Positioner / Desalter Effluent Water Outlet E-314	HB-U-I	INSTRUMENTATION HSD-E 314			ARLPHWD
PP-P1-199	Pressure Gauge / Before Engine (Fuel Oil)	PP	INSTRUMENTATION PP-ENG 100			ARLPHWD
PP-PXL-150	Pressure Alarm / Nozzle Cooling Oil Inlet Pressure	PP	INSTRUMENTATION PP-ENG 100			ARLPHWD

Asset: Used to create, update, and maintain detailed asset information, including its status, location, parent asset structure, serial number, vendor details, and operating costs.



Asset: PP-TI-202A Water Tube Boiler Site: ARLPHWD

Status: OPERATING Asset Template: Safety Critical: ☐ Moved: ☐ Returned to Vendor: ☐

Details

Parent: PP-ENG 200 POWER PLANT ENGINE NO.2 Calendar: Section: Shift: Priority: Serial #

Asset Type: INSTRUMENT


Maintain Hierarchy? ☐

Location: PP Power Plant Bin: Rotating Item: Condition Code: Meter Group: Default Repair Facility: Repair Facility Site:

Purchase Information

Vendor: Total Cost: 0.00

Spare Parts: Used to manage and track the subassemblies, spare parts, available inventory quantities, and associated item components required to maintain the asset.



Asset	Description	Quantity Available	IssuedQty	Remarks
There are no rows to display.				


Subassemblies

Asset	Description
There are no rows to display.	


Spare Parts

Item	Description	Quantity Available	IssuedQty	Remarks
There are no rows to display.				


Safety: Used to manage and maintain safety-related information for an asset, including hazards and precautions, hazardous materials, Lock Out/Tag Out (LOTO) procedures, and safety-related assets.




Meters: Used to enter, view, and track meter readings, meter groups, meter types, unit of measure, and active life-to-date meter information associated with an asset.




Specifications: Used to define and maintain detailed technical attributes, classification values (alphanumeric, numeric, date), and units of measure specific to the asset type.




Relationships: Used to view, create, and manage connections between assets, defining source and target asset dependencies and relationships.



Work: Used to view, track, and manage open and historical work orders and service tickets associated with the asset.



Service Address: Used to view, manage, and maintain physical location details, geographic coordinates (latitude and longitude), street addresses, and routing directions associated with the asset.




METERS

The Meters application is used to define meters and track the usage, life-to-date history, and consumption data for assets and locations.

The three types of meters are:

1. **Continuous:** Measures cumulative readings over time, such as operating hours, kilometers/miles, engine starts, and fuel consumed.
2. **Gauge:** Measures variable conditions at a specific point in time, such as oil pressure, fuel level, temperature, and noise level.
3. **Characteristic:** Tracks qualitative observations or physical conditions, such as vibration quality, noise levels, and color ratings.



The screenshot shows the 'Meters' application interface. On the left is a sidebar with navigation options like 'Go To Applications', 'Available Queries', 'All Records', 'All Bookmarks', 'Common Actions' (New Meter, Create KPI, Create Report), and 'More Actions' (Unit of Measure and Conversion, Run Reports, Cognos Analytics). The main area displays a table of meters with columns for Meter ID, Description, and Meter Type. The table lists various meters such as 'Running hours Meter for PH-P 586 (AGL FFO Pump)', 'Running Hours Meter', 'vibration meter', and 'Kilometer for vehicles'.

Meter	Description	Meter Type
RH-PH-P586	Running hours Meter for PH-P 586 (AGL FFO Pump)	CONTINUOUS
RH-PH-P583	Running hours Meter for PH-P-583 at Tk - 14 - Pump	CONTINUOUS
RH-PH-P587	Running hours meter for PH-P 587 (AGL FFO Pump)	CONTINUOUS
RH-PH-P588	Running hours meter for PH-P 588 (AGL FFO Pump)	CONTINUOUS
COND		GAUGE
HOURSARLM	Running Hours Meter	CONTINUOUS
HOURS-MTR	Running Hours Meter	CONTINUOUS
RUN-HOUR	A	CONTINUOUS
VIB-METER	vibration meter	CHARACTERISTIC
RH-PH-P584	Running hours meter for PH-P-584 Transfer pump house	CONTINUOUS
RH-PH-P585	Running hours meter for PH-P-585 Transfer pump house	CONTINUOUS
SR	SR	GAUGE
VB-1-V	Vibration of Motor inboard Vertical (M1V)	GAUGE
VB-2-H	Vibration of Motor outboard Horizontal (M2H)	GAUGE
VB-2-A	vibration of Motor outboard Axial (M2A)	GAUGE
VB-3-A	vibration of Pump inboard Axial (P3A)	GAUGE
KM-METER	Kilometer for vehicles	CONTINUOUS


LOCATIONS

The Locations application is a site-level application used to create and manage records for physical places where assets are operated, stored, or repaired. It allows organizations to track asset movements, manage maintenance records at specific physical sites, and build hierarchical or networked systems.

The primary types of locations include:

1. **Operating:** Places where assets are actively installed, operated, and maintained (e.g., plants, buildings, or production lines).
2. **Vendor:** Locations representing external suppliers, manufacturers, or outside repair facilities.
3. **Repair:** Internal maintenance shop locations designated for repairing equipment and subassemblies.
4. **Holding / Courier:** Staging areas or transit locations used when assets are being transferred, shipped, or stored temporarily.

5. **Salvage:** Locations designated for decommissioned, retired, or scrapped assets.




The screenshot shows the 'Locations' application interface. On the left is a sidebar with navigation items like 'Go To Applications', 'Available Queries', 'Common Actions', and 'More Actions'. The main area displays a table of locations. The table has columns: Location, Description, Type, Status, Priority, and Site. The data is filtered to show 1 of 1799 records.

Location	Description	Type	Status	Priority	Site
AB	Asphalt Blending Plant	OPS-PLANT	OPERATING		ARLPWD
AC-WKSP	Air-Conditioning Workshop	WORKSHOP	OPERATING		ARLPWD
ACK585	Toyota Yaris allocated to Mr. Khaleeq-uz-Zaman Senior Manager (Technical)	FACILITY	OPERATING	2	ARLPWD
AE-SD	Attock Energy site office workshop near OM-II	RESID-BUILDING	OPERATING		ARLPWD
AGL-WATER-HARVESTING	AGL WATER HARVESTING	RESID-BUILDING	OPERATING		ARLPWD
AGL(GW)	ATTOCK GEN. LIMITED (GENERAL WORK ORDERS)	OPS-PLANT	OPERATING		ARLPWD
AGL(OSBL)	ATTOCK GEN. LIMITED (OSBL WORK ORDERS)	OPS-PLANT	OPERATING		ARLPWD
AH	Attock House	OFF-BUILDING	OPERATING		ARLPWD
AHL	Attock Hospital Limited	HOSPITAL	OPERATING		ARLPWD
AHL-PHARMACY	AHL Pharmacy	RESID-BUILDING	OPERATING		ARLPWD
AHL-OPD-B-5A/1	AHL-OPD (Subline Bungalow 5 A/1)	HOSPITAL	OPERATING		ARLPWD
AHL-OPD-B-5A/2	(SUBLINE BUNGALOW 5 A/2)	HOSPITAL	OPERATING		ARLPWD
AJM-589	YARIS ATIV CVT allocated to CEO	FACILITY	OPERATING		ARLPWD
AJM-588	YARIS GLI CVT allocated to Mr. Usman Ali Khan	FACILITY	OPERATING		ARLPWD
AIX-233	YARIS GLI CVT allocated to Mr. Habib Anwar	FACILITY	OPERATING		ARLPWD
AIX-595	YARIS GLI CVT allocated to Mr. Saeed ud Din Faruqi	FACILITY	OPERATING		ARLPWD
AIX-623	YARIS GLI CVT allocated to Mr. Khalid Mehmood	FACILITY	OPERATING		ARLPWD
AIX-919	YARIS GLI CVT allocated to Mr. Anshad Hayee Khan	FACILITY	OPERATING		ARLPWD

Condition Monitoring

The Condition Monitoring application is used to create and view measurement point records for assets and locations, establishing acceptable limits for gauge or characteristic meter readings to automatically trigger preventive maintenance (PM) work orders or job plans when readings fall outside safe thresholds



The screenshot shows the 'Condition Monitoring' application interface. On the left is a sidebar with navigation items like 'Go To Applications', 'Available Queries', 'Common Actions', and 'More Actions'. The main area displays a table of measurement points. The table has columns: Point, Description, Location, Asset, Motor, and Site. The data is filtered to show 1 of 7781 records.

Point	Description	Location	Asset	Motor	Site
AMU-LP-101R-3H	Pump Inboard Horizontal (P3H)		AMU-LP-101R	VB-3-H	ARLPWD
AMU-P-100B-1V	Motor Outboard Horizontal (M1H)		AMU-P-100B	VU-1-H	ARLPWD
HYU-LP-103A-2H	Motor Inboard Horizontal (M2H)		HYU-LP-103A	VB-2-H	ARLPWD
HDS-P-001A-1V	Motor Outboard Vertical (M1V)		HDS-P-001A	VB-1-V	ARLPWD
HDS-P-001A-2H	Motor Inboard Horizontal (M2H)		HDS-P-001A	VB-2-H	ARLPWD
HDS-P-001A-4H	Pump outboard Horizontal (P4H)		HDS-P-001A	VB-4-H	ARLPWD
HYU-P-100A-4H	Pump outboard Horizontal (P4H)		HYU-P-100A	VB-4-H	ARLPWD
HYU-LP-100B-2V	Motor Inboard Vertical (M2V)		HYU-LP-100B	VB-2-V	ARLPWD
ITU-P-100B-3H	Pump Inboard Horizontal (P3H)		ITU-P-100B	VB-3-H	ARLPWD
HYU-LP-101A-1A	Motor Outboard Axial (M1A)		HYU-LP-101A	VB-1-A	ARLPWD
ITU-P-101A-4V	Pump outboard Vertical (P4V)		ITU-P-101A	VU-4-V	ARLPWD
HYU-LP-101R-3A	Motor Inboard Axial (M3A)		HYU-LP-101R	VB-3-A	ARLPWD
ITU-P-101B-4V	Pump outboard Vertical (P4V)		ITU-P-101B	VU-4-V	ARLPWD
HYU-LP-101A-R-P3A-2H	Motor Inboard Horizontal (M2H)		HYU-LP-101A-R-P3A	VB-2-H	ARLPWD
HC-P-011B-1V	Motor Outboard Vertical (M1V)		HC-P-011B	VB-1-V	ARLPWD
HC-P-011B-3H	Pump Inboard Horizontal (P3H)		HC-P-011B	VB-3-H	ARLPWD
HC-P-011B-3A	Pump Inboard Axial (P3A)		HC-P-011B	VB-3-A	ARLPWD
AMU-P-100B-1V	Motor Outboard Vertical (M1V)		AMU-P-100B	VB-1-V	ARLPWD

Failure Codes

The Failure Codes application is used to build and manage structured failure hierarchies consisting of Problem, Cause, and Remedy levels—to categorize asset and location failures, analyze breakdown causes, and improve equipment reliability across the organization.

- **Failure Classes:** Used to search, filter, and view high-level failure classifications, displaying key details such as failure class ID, description, and organization.

The screenshot displays the 'Failure Codes' application interface. The top navigation bar includes a home icon, a menu icon, and the title 'Failure Codes'. Below the navigation bar is a search bar labeled 'Find Failure Code' and a toolbar with icons for document, save, edit, and refresh. The left sidebar contains a 'Find Navigation Item' search bar, a 'Go To Applications' button, and a list of 'Available Queries' including 'All Records' and 'All Bookmarks'. Under 'Common Actions', there are buttons for 'New Failure Code', 'Create KPI', and 'Create Report'. Under 'More Actions', there are links for 'Attachment Library/Folders', 'Run Reports', and 'Cognos Analytics'. The main content area is titled 'Failure Classes' and features a table with columns for 'Failure Class', 'Description', and 'Organization'. The table lists various failure classes, with 'STEAM-TRAP-FAIL' highlighted. A status bar at the bottom of the table indicates '1 - 20 of 70' records.

Failure Class	Description	Organization
STEAM-TRAP-FAIL	Steam trap failures	ARL
CLEANER-20300	Portable Tube Cleaning Machine Failures	ARL
PU	Pump Failures	ARL
AGITATOR-33000	Agitator / Mixer Failures	ARL
CNTRL-PNL-21000	Control Panel Failures	ARL
POW-TRAFO-21500	Power Transformer Failures	ARL
ACC-PROBE-10000	Acceleration Probe Failures	ARL
BATTBANK-10200	Battery Bank Failures	ARL
BD-VALVE-10500	Blowdown Valve Failures	ARL
CABL-TRAY-22300	Cable Trays Failures	ARL
CF-VESSEL-33150	Coalescer Filter Vessel Failures	ARL
COLUMN-33200	Column Failures	ARL
CNT-VALVE-11000	Control Valve Failures	ARL
COR-MONTR-40000	Corrosion Monitors (Corrosion Probe) Failures	ARL
DC-CHARGR-11200	DC Charger Failures	ARL
DIESEL-ENG-33400	Diesel Engine Failures	ARL
DPR-GAUGE-11500	Differential Pressure Gauge Failures	ARL
DPSWITCH-11700	Differential Pressure Switch Failures	ARL

PREVENTIVE MAINTENANCE

PREVENTIVE MAINTENANCE

What is Preventive Maintenance?

Preventive Maintenance (PM) is scheduled maintenance performed regularly to keep assets working properly and reduce the chances of unexpected failures. In Maximo, it helps plan the required labor, materials, services, and tools for regular maintenance and inspection work.

The Preventive Maintenance module has two main applications:

- Preventive Maintenance: Used to plan and schedule periodic maintenance and inspections for assets and locations.
- Master PM: Used to create general preventive maintenance templates that can be used for different assets and locations.

Master PM Records

A Master PM is a general template used to create related Preventive Maintenance records. It can be used for common maintenance or inspection activities that are performed on multiple assets or locations.

A Master PM itself does not generate work orders. Instead, it is used to create related PM records in the Preventive Maintenance application. These PM records contain site-specific information and are then used to generate work orders for the required maintenance activities.

Master PM Application

The Master PM application is used to create and manage general PM templates for recurring maintenance and inspection activities.

Preventive Maintenance Records

A Preventive Maintenance (PM) record defines the planned maintenance or inspection work to be performed on an asset or location. The schedule can be based on factors such as time, meter readings, or seasonal dates.

PM records are used to determine when the maintenance work should be performed and help Maximo generate the required work orders.

Preventive Maintenance Tabs:

1. **List View:** Used to search, filter, and view existing PM records.
2. **PM:** Used to enter, view, or modify primary PM details and associate them with assets, locations, routes, or job plans.
3. **Frequency:** Used to define time-based or meter-based frequency criteria for triggering scheduled work orders.
4. **Seasonal Dates:** Used to specify active seasonal periods, months, or days when the PM is eligible to run.
5. **Job Plan Sequence:** Used to sequence multiple job plans so tasks rotate or escalate across successive PM cycles.
6. **PM Hierarchy:** Used to establish parent-child PM relationships to generate structured work order hierarchies.
7. **Forecast:** Used to project future maintenance due dates and schedules based on frequency criteria.
8. **Forecast Cost:** Used to estimate projected labor, material, tool, and service costs for forecasted PM cycles.
9. **Work:** Used to view open and completed work orders generated from the PM record.

List

The screenshot displays the 'Preventive Maintenance' software interface. The top navigation bar includes tabs for 'List View', 'PM', 'Frequency', 'Seasonal Dates', 'Job Plan Sequence', 'PM Hierarchy', 'Forecast', 'Forecast Cost', and 'Work'. The 'List View' tab is active, showing details for PM 3423, 'Servicing and overhauling of FlowMeter', at site ARLPWD. The status is 'INACTIVE'. The interface is divided into several sections: 'Details' (Location, Asset, Route, Department/Section, Inspection Type), 'Work Order Information' (Job Plan, Work Type, Work Order Status, Priority, Interruptible), 'Responsibility' (Supervisor, Crew, Lead, Owner, Owner Group, Crew Work Group), and 'Resource Information'. The left sidebar contains navigation options like 'Go To Applications', 'Available Queries', 'All Records', 'All Bookmarks', 'Common Actions', and 'More Actions'.

Frequency

The screenshot displays the 'Preventive Maintenance' software interface with the 'Frequency' tab active. It shows the same PM record (PM 3423, 'Servicing and overhauling of FlowMeter', site ARLPWD, status INACTIVE). The 'Work Order Generation Information' section is prominent, with checkboxes for 'Use Last Work Order's Start Date to Calculate Next Due Date?' and 'Generate Work Order Based on Meter Readings (Do Not Estimate?)'. Below this, there are two tabs: 'Time Based Frequency' and 'Meter Based Frequency'. The 'Time Based Frequency' tab is selected, showing fields for 'Frequency' (set to 1), 'Alert Lead (Days)' (set to 0), 'Extended Date', 'Target Start Time', 'Frequency Units' (set to YEARS), 'Estimated Next Due Date' (11/5/12), and 'Adjust Next Due Date?'. The left sidebar is identical to the previous screenshot.

Seasonal Dates

Find PM

Find Navigation Item

Go To Applications

Available Queries

All Records

All Bookmarks

BH Compressions

PPlant Active PMs

PM Schedule with One year look ahe...

WITH Meter based PMs

WITH Time Based PMs

Common Actions

New PM

Save PM

Clear Changes

Create Report

More Actions

View Sequence

Generate Work Orders

Set Reading At Last W/O

Lock Forecast Dates

Unlock Forecast Dates

Attachment Library/Folders

Duplicate PM

Add to Bookmarks

Seasonal Dates

PM 3423 Servicing and overhauling of FlowMeter Site ARLPWD Status INACTIVE Forecast Exists?

Active Days

Sunday? Monday? Tuesday? Wednesday? Thursday? Friday? Saturday?

Schedule Early on Frequency Conflict?

Active Time

Target Start Time

Active Dates

0 - 0 of 0

Start Month Start Day End Month End Day

There are no rows to display

New Row

Preventive Maintenance

Find PM

Find Navigation Item

Go To Applications

Available Queries

All Records

All Bookmarks

BH Compressions

PPlant Active PMs

PM Schedule with One year look ahe...

WITH Meter based PMs

WITH Time Based PMs

Common Actions

New PM

Save PM

Clear Changes

Create Report

More Actions

View Sequence

Generate Work Orders

Set Reading At Last W/O

Lock Forecast Dates

Unlock Forecast Dates

Attachment Library/Folders

Duplicate PM

Add to Bookmarks

Job Plan Sequence

PM 3423 Servicing and overhauling of FlowMeter Site ARLPWD Status INACTIVE Forecast Exists?

Location

Asset TEL-PM 01

Job Plan PROV-PO

Job Plan Sequence

1 - 1 of 1

Job Plan Description Total Work Units Sequence

PROV-PO Proving of PD Meter 1.00 1

New Row

PH Hierarchy

Find PM

Find Navigation Item

Go To Applications

Available Queries

All Records

All Bookmarks

BH Compressions

PPlant Active PMs

PM Schedule with One year look ahe...

WITH Meter based PMs

WITH Time Based PMs

Common Actions

New PM

Save PM

Clear Changes

Create Report

More Actions

View Sequence

Generate Work Orders

Set Reading At Last W/O

Lock Forecast Dates

Unlock Forecast Dates

Attachment Library/Folders

Duplicate PM

Add to Bookmarks

PM Hierarchy

PM 3423 Servicing and overhauling of FlowMeter Site ARLPWD Status INACTIVE Forecast Exists?

Parent

Children

0 - 0 of 0

Sequence PM Description Asset Location Status

There are no rows to display

New Row

Forecast

Find PM

Find Navigation Item

Go To Applications

Available Queries

All Records

All Bookmarks

BH Compressions

P-Plant Active PM's

PM Schedule with One year look ahe...

WTH Meter based PM's

WTH Time Based PM's

Common Actions

New PM

Save PM

Clear Changes

Create Report

More Actions

View Sequence

Generate Work Orders

Set Reading At Last WO

Lock Forecast Dates

Unlock Forecast Dates

Attachment Library/Folders

Duplicate PM

Add to Bookmarks

Preventive Maintenance

PM

Frequency

Seasonal Dates

Job Plan Sequence

PM Hierarchy

Forecast

Forecast Cost

Work

Find PM

Find Navigation Item

Go To Applications

Available Queries

All Records

All Bookmarks

BH Compressions

P-Plant Active PM's

PM Schedule with One year look ahe...

WTH Meter based PM's

WTH Time Based PM's

Common Actions

New PM

Save PM

Clear Changes

Create Report

More Actions

View Sequence

Generate Work Orders

Set Reading At Last WO

Lock Forecast Dates

Unlock Forecast Dates

Attachment Library/Folders

Duplicate PM

Add to Bookmarks

Forecast Cost

Find PM

Find Navigation Item

Go To Applications

Available Queries

All Records

All Bookmarks

BH Compressions

P-Plant Active PM's

PM Schedule with One year look ahe...

WTH Meter based PM's

WTH Time Based PM's

Common Actions

New PM

Save PM

Clear Changes

Create Report

More Actions

View Sequence

Generate Work Orders

Set Reading At Last WO

Lock Forecast Dates

Unlock Forecast Dates

Attachment Library/Folders

Duplicate PM

Add to Bookmarks

Preventive Maintenance

PM

Frequency

Seasonal Dates

Job Plan Sequence

PM Hierarchy

Forecast

Forecast Cost

Work

Find PM

Find Navigation Item

Go To Applications

Available Queries

All Records

All Bookmarks

BH Compressions

P-Plant Active PM's

PM Schedule with One year look ahe...

WTH Meter based PM's

WTH Time Based PM's

Common Actions

New PM

Save PM

Clear Changes

Create Report

More Actions

View Sequence

Generate Work Orders

Set Reading At Last WO

Lock Forecast Dates

Unlock Forecast Dates

Attachment Library/Folders

Duplicate PM

Add to Bookmarks

Work

Find PM

Find Navigation Item

Go To Applications

Available Queries

All Records

All Bookmarks

BH Compressions

P-Plant Active PM's

PM Schedule with One year look ahe...

WTH Meter based PM's

WTH Time Based PM's

Common Actions

New PM

Save PM

Clear Changes

Create Report

More Actions

View Sequence

Generate Work Orders

Set Reading At Last WO

Lock Forecast Dates

Unlock Forecast Dates

Attachment Library/Folders

Duplicate PM

Add to Bookmarks

Preventive Maintenance

PM

Frequency

Seasonal Dates

Job Plan Sequence

PM Hierarchy

Forecast

Forecast Cost

Work

Find PM

Find Navigation Item

Go To Applications

Available Queries

All Records

All Bookmarks

BH Compressions

P-Plant Active PM's

PM Schedule with One year look ahe...

WTH Meter based PM's

WTH Time Based PM's

Common Actions

New PM

Save PM

Clear Changes

Create Report

More Actions

View Sequence

Generate Work Orders

Set Reading At Last WO

Lock Forecast Dates

Unlock Forecast Dates

Attachment Library/Folders


Duplicate PM

Add to Bookmarks

Master PM

The Master PM application is used to define generic PM templates that can be applied to multiple, similar assets or locations, reducing data entry time and ensuring consistency across maintenance plans.


- **List View (Master PMs):** Used to search, filter, and view existing Master PM records, displaying details such as the Master PM ID, description, associated item, and item set.



Preventive Maintenance

The Preventive Maintenance application is used to create and manage PM records for specific assets or locations, acting as templates to automatically generate scheduled work orders based on time or meter frequencies.

- **List View (PMs):** Used to search, filter, and view existing PM records, displaying details such as the PM ID, description, priority, location, asset, department/section, forecast status, and site.



Creating Preventive Maintenance Records

PM records are used to define scheduled maintenance activities and generate work orders for assets or locations. A PM can be generated individually, in batches, or automatically according to the defined schedule.

Procedure

1. Open the Preventive Maintenance application and select New PM to create a new PM record.
2. Enter the PM number and provide a suitable Description for the maintenance activity.
3. Select the required Asset or Location for which the maintenance is to be performed.
4. If required, select a Route to apply the PM to assets included in a specific maintenance or inspection route.
5. Set the required PM options, such as status inheritance and PM hierarchy, according to the maintenance requirement.
6. Open the Frequency tab and define when the work order should be generated. The frequency can be based on:
 - Time
 - Meter readings
 - Both time and meter readings
7. If required, configure seasonal dates to generate maintenance work orders during a specific period or planned shutdown.
8. In the Job Plan Sequence tab, select the required job plan and define any related clearance or impact plan requirements.
9. If the PM is part of a PM hierarchy, define the related child PM records.
10. Review the entered information and click Save PM to save the preventive maintenance record.


PURCHASE MODULE

Purchasing application

The Purchasing Module is one of the Maximo modules devoted to financial and purchasing functions. The Purchasing Module tracks requests for and purchases of materials and services, receipt of the purchases, and invoices for the purchases. The purchasing module has following applications

Purchasing Applications

- **Companies:** Used to maintain information about vendors, manufacturers, and other companies that work with the organization.
- **Company Master:** Used to define and manage companies within a shared Company Set.
- **Invoices:** Used to record invoices and match them with purchase orders and received items or services.
- **Purchase Requisitions:** Used to request materials or services that need to be purchased.
- **Receiving:** Used to record received materials and services in the system.
- **Request for Quotations:** Used to request and manage vendor quotations, including prices and delivery details.



Purchase requisition:

The **Purchase Requisitions** application is used to create and manage requests for materials and services that need to be purchased. It can be accessed from the Start Center or through **Go To → Purchasing → Purchase Requisitions**.

Purchase Requisitions Tabs

- **List:** Used to search and view existing purchase requisitions.
- **PR:** Used to create, view, and update purchase requisition details.
- **PR Lines:** Used to add and manage the items, materials, or services required in a requisition.
- **Ship To/Bill To:** Used to enter shipping and billing information.
- **Terms and Conditions:** Used to add or manage terms and conditions related to the requisition.
- **Log:** Used to view activity history, work logs, and communication records.
- **Specifications:** Used to enter technical specifications and required attributes for requested items.
- **Related Records:** Used to view purchasing documents related to the requisition, such as POs, RFQs, receipts, inspections, invoices, and contracts.

List

The screenshot shows the 'Purchase Requisition' list in SAP. The table displays various requisitions with columns for PR#, Description, Status, Company, Department/Section, Type, Requested Date, Issue Date, and Src. The list includes items like 'Instruments For Lumex ESD system', 'Spares required for power plant', and 'Power plant temp gauges'. The status of the requisitions varies, including 'APPR' (Approved for Purchase) and 'ARL' (Approved for Release).

PR#	Description	Status	Company	Department/Section	Type	Requested Date	Issue Date	Src
2256	Instruments For Lumex ESD system	APPR	2110	MAINT/PLANT	LOCAL BUDGET	11/17/08 1:12 PM	9/17/08 12:47 PM	ARL/PWD
2554	Spares required for power plant	APPR		MAINT/PLANT	LOCAL		12/31/08 10:10 AM	ARL/PWD
2342	Replacement of damage Computer key board and mouse	APPR		CA/MGMT	LOCAL		1/14/09 12:03 PM	ARL/PWD
2425	Power plant temp gauges (Suppliers names list given in description)	APPR		MAINT/INST	LOCAL	1/26/09 10:49 AM	1/14/09 10:30 AM	ARL/PWD
2627	Motor and particle pumps at NRUs	APPR	9343	MAINT/INST			5/11/09 9:57 AM	ARL/PWD
3113	DELL Precision Workstation	APPR		MAINT/INST			2/4/09 9:52 AM	ARL/PWD
2800220	BUDGET ITEMS	APPR			LOCAL BUDGET		7/21/08 9:18 PM	ARL/PWD
2800240	BUDGET ITEMS	APPR			LOCAL BUDGET		7/22/08 9:55 AM	ARL/PWD
2800244	BUDGET ITEMS	APPR			LOCAL BUDGET		7/22/08 10:15 AM	ARL/PWD
5000610	REQUIRED FOR STOCK	APPR			STATIONARY		7/22/08 10:38 AM	ARL/PWD
5000615	REQUIRED FOR STOCK	APPR			STATIONARY		7/22/08 10:38 AM	ARL/PWD
5000620	REQUIRED FOR STOCK	APPR			STATIONARY		7/22/08 11:38 AM	ARL/PWD
5000625	REQUIRED FOR STOCK	APPR			STATIONARY		7/22/08 12:41 PM	ARL/PWD
5000642	REQUIRED FOR STOCK	APPR			STATIONARY		7/22/08 12:44 PM	ARL/PWD
13000200	REQUIRED FOR NONSTOCK	APPR			LOCAL		7/22/08 2:02 PM	ARL/PWD
13000227	REQUIRED FOR NONSTOCK	APPR			LOCAL		7/22/08 2:07 PM	ARL/PWD
4806	Misc. tools for Maintenance (CM 03/10)	APPR		MAINT/PLANT	LOCAL BUDGET		5/17/09 2:12 PM	ARL/PWD
4854	DELL Precision Workstation	APPR	9343	MAINT/INST			9/16/09 11:52 AM	ARL/PWD

PR

The screenshot shows the 'Purchase Requisition' details in SAP. The form displays the requisition number (pr 2975) and the description 'Power plant temp gauges'. It includes fields for Status (APPR), Stock Category (NS), Category (Local PR), and Category (Foreign PR) (NON-BUDGET). The 'Details' section shows the origin (Inst Dept/Section: MAINT/INST), entered by (11432), requested by name (Mr. Usman Ali Khan), reviewed by (SI), and reviewed by (SI). The 'Vendor' section shows the company (No Vendor?), address, city, state/province, ZIP/postal code, and contact. The 'Costs' section shows the price total (0.00), total tax (0.00), total cost (0.00), currency (PKR), and total base cost (0.00). The 'Workflow History' section shows a list of users and their assignment dates.

Name	Assignment Date
Mr. Salman Tariq	2/9/09 2:35 PM
Mr. Muhammad Rizwanullah Tahir	2/9/09 2:35 PM
Mr. Muhammad Rizwanullah Tahir	10/10/09 12:02 PM
Mr. Usman Ali Khan	10/10/09 12:02 PM
Mr. Muhammad Rizwanullah Tahir	10/10/09 12:02 PM
Mr. Ahmed Naveed	10/10/09 12:02 PM

PR Lines

Ship To / Bill To

Terms and Conditions

Log

Purchase Requisition

Find PR

Find Navigation Item

Go To Applications

Available Queries

- All Records
- All Bookmarks
- Current Assignments (PR)
- INST PR
- IT PRs
- Outstanding PRs (FIN-YEAR)
- Outstanding PRs FOREIGN

Common Actions

- New Purchase Requisition
- Save Purchase Requisition
- Clear Changes
- Change Status
- Create Report

More Actions

- Workflow
- PR Hard Closed
- View History
- Create PO
- Create Contract
- View Related Records

PR 2975 Power plant temp gauges (Suppliers names list given in des) Site ARLPWD Status APPR Total Cost 0.00

Work Log

Communication Log

Work Logs

Record Class Created By Date Type Summary Viewable?

There are no rows to display.

New Row

Specifications

Purchase Requisition

Find PR

Find Navigation Item

Go To Applications

Available Queries

- All Records
- All Bookmarks
- Current Assignments (PR)
- INST PR
- IT PRs
- Outstanding PRs (FIN-YEAR)
- Outstanding PRs FOREIGN

Common Actions

- New Purchase Requisition
- Save Purchase Requisition
- Clear Changes
- Change Status
- Create Report

More Actions

- Workflow
- PR Hard Closed
- View History
- Create PO
- Create Contract
- View Related Records

PR 2975 Power plant temp gauges (Suppliers names list given in des) Site ARLPWD Status APPR Total Cost 0.00

Attributes

Line Item Attribute Description Data Type Date Value Alphanumeric Value Numeric Value Unit of Measure Table Value

There are no rows to display.

Related Records

Purchase Requisition

Find PR

Find Navigation Item

Go To Applications

Available Queries

- All Records
- All Bookmarks
- Current Assignments (PR)
- INST PR
- IT PRs
- Outstanding PRs (FIN-YEAR)
- Outstanding PRs FOREIGN

Common Actions

- New Purchase Requisition
- Save Purchase Requisition
- Clear Changes
- Change Status
- Create Report

More Actions

- Workflow
- PR Hard Closed
- View History
- Create PO
- Create Contract
- View Related Records

POs RFQs Material Receipts Inspection Invoices Invoice Transactions Contract References

POs

Line PO Revision Line Item Description Quantity Order Line Status Site Requested By

There are no rows to display.

Purchase Order

A purchase order (PO) is an authorized order from a purchasing agent or department to an internal supplier or external vendor. The Purchase Orders application also allows you to generate an internal PO against another storeroom. You can think of a storeroom-to-storeroom purchase as a *transfer order* or an *internal PO* because IBM Maximo Asset Management uses the Purchase Orders and Issues and Transfers applications to track these types of item movements. You also use Purchase Contracts application to create change orders.

To access the Purchase Order application, click the application link on your Start Center, or select **goto** → **Purchasing** → **Purchase Orders**.

The Purchase Orders application contains the following tabs:

- **List:** Use this tab to search PR records.
- **PO:** Use this tab to enter, view, or modify purchase Orders.
- **PO Lines:** Use this tab to enter, view, or modify line items for a purchase Order. A line can be an item or material from inventory, an item or material not from inventory, or a service.
- **Ship To/Bill To:** Use this tab to enter, view, or modify shipping information that will be used as a default on each line, and billing information for the entire order.
- **Terms and Conditions:** Use this tab to add, view, or delete terms and conditions that have been associated with the record.

List

PO#	Description	Category	Status	Delivery Date	Supplier Name	Total Cost	Revision	Receipts
ASL24447		LOCAL	WAPPR		SUNSTRAND INTERNATIONAL S.A	434,384.00	0	NONE
ASL24185		LOCAL	WAPPR			0.00	0	NONE
ASL23031		LOCAL BUDGET	WAPPR		MTSUBISHI ISLAMABAD MOTORS	3,000.00	0	NONE
ASL24486	PRINTING STATIONARY FOR SECURITY	LOCAL	WAPPR			0.00	0	NONE
ASL22496		LOCAL	WAPPR			0.00	0	NONE
ASL23086		LOCAL	WAPPR			0.00	0	NONE
ASL23922		LOCAL	WAPPR			0.00	0	NONE
ASL26346		LOCAL	WAPPR		FLOUREAL SPECIALITY VALVES	0.00	0	NONE
ASL25842	STEEL STRUCTURE	LOCAL	WAPPR			0.00	0	NONE
ASL23653		LOCAL	WAPPR			0.00	0	NONE
ASL23625		LOCAL	WAPPR			0.00	0	NONE
ASL23621	PO25 4:24 PM MISC. STATIONARY ITEMS	STATIONARY	WAPPR		NEW IDEAL STATIONERS	524,306.60	0	NONE
ASL23627	3/20/25 11:20 AM	LOCAL	APPR		ALLIED PIPING INC	11,800.00	1	NONE
ASL23627	3/20/25 11:20 AM	LOCAL	PNDRIV		ALLIED PIPING INC	11,800.00	2	NONE
ASL23625	3/12/25 9:19 AM Green metal	LOCAL	WAPPR		MTSUBISHI ISLAMABAD MOTORS	0.00	0	NONE
ASL23623	3/12/25 9:16 AM	LOCAL	WAPPR			0.00	0	NONE
ASL23624	12/3/24 10:43 AM	LOCAL	APPR		MTSUBISHI ISLAMABAD MOTORS	333.00	0	NONE
ASL23623	12/3/24 10:25 AM	LOCAL	APPR		MTSUBISHI ISLAMABAD MOTORS	100,000.00	0	NONE

PO

Purchase Order Local

Find PO

Find Navigation Item

Go To Applications

Available Queries

All Records

All Bookmarks

All Purchase Orders

Local Budget Data for Current Month

Local Non-Budget Data for Current Month

Outstanding POs Local (FIM-YEAR)

PO LOCAL BUDGET AND STATIONERS

PO Local Last month data

PO Local Budget Monthly Data

Common Actions

New Purchase Order

Change Status

Create KPI

Create Report

More Actions

Copy PO Line Items to PO

List of Materials and Components

Attachability Commodity Codes

Attachment Library/Patterns

Risk Reports

Previous Application

PO# ASL23627

PO Category LOCAL

Block Category 28

Type STD

Company 2798

NT# 42201-001167

Buyer

Vendor Quote Refr

Revision 1

Tax Code

PO TAX (LINES)

Date

Status Date 3/10/25 11:09 AM

Ordered Date 3/20/25 11:20 AM

Due Date

Follow-up Date

Vendor

Address SUIT # 401, 4TH FLOOR, THE FORUM G-26, BLOCK-B, C

Buyer Company ARS

Our Ref

Exchange Rate 1.000000

Status APPR

GST/Wght Revision?

ARS REC Check?

Attached Documents

There are no 1

Costs

Pre-tax Total 10,800.00

GST 1,800.00

E.O. 0.00

Other Taxes 0.00

Discount 0.00

Total Cost 11,800.00

Terms

Delivery Terms F.O.B.

Payment Terms Credit

Remarks Payment Term

Freight Terms

Details

Original PO

PO Lines

Purchase Order Local

Find PO

Find Navigation Item

Go To Applications

Available Queries

All Records

All Bookmarks

All Purchase Orders

Local Budget Data for Current Month

Local Non-Budget Data for Current Month

Outstanding POs Local (FIN-YEAR)

Outstanding POs Local (FIN-YEAR)

Common Actions

New Purchase Order

Save Purchase Order

Clear Changes

Change Status

Approve Purchase Order

Close Purchase Order

More Actions

Workflow

View History

Copy PR Line Items To PO

Create Contract

Complete Receipts

PO: ARL/2627 33333

Company: 2798 ALLIED PIPING INC

Currency: PKR

Site: ARLPWD

Status: APPR

Total Cost: 11,800.00

Revision: 1

PO Lines

Line	PRM	Item	Description	Order Line	Quantity	Unit Cost	Tax	E.D	Line Cost
1	30407	25365	REDUCER CONCENTRIC 6" X 9" SCH-40 A	NUMBER	2.00	5,000.00	1,800.00	0.00	10,000.00

Vendor Items Contract Items Select Spare Parts Vendor Analysis View Contracts Distribute Costs New Row

Ship To / Bill To

Purchase Order Local

Find PO

Find Navigation Item

Go To Applications

Available Queries

All Records

All Bookmarks

All Purchase Orders

Local Budget Data for Current Month

Local Non-Budget Data for Current Month

Outstanding POs Local (FIN-YEAR)

Outstanding POs Local (FIN-YEAR)

Common Actions

New Purchase Order

Save Purchase Order

Clear Changes

Change Status

Approve Purchase Order

Close Purchase Order

More Actions

Workflow

View History

Copy PR Line Items To PO

Create Contract

Complete Receipts

PO: ARL/2627 33333

Revision: 1

Site: ARLPWD

Status: APPR

Total Cost: 11,800.00

Ship To

Delivery At: ARL Attock Refinery Limited

Address: Morgah

City: Rawalpindi

State/Province: Pakistan

ZIP/Postal Code: 46000

Attention: 113758 Mr. Shafique Rehman Paracha

Destination:

Bill To

Bill To: ARL Attock Refinery Limited

Address: Morgah

City: Rawalpindi

State/Province: Pakistan

ZIP/Postal Code: 46000

Attention: 113758 Mr. Shafique Rehman Paracha

Destination:

Term and Conditions

Purchase Order Local

Find PO

Find Navigation Item

Go To Applications

Available Queries

All Records

All Bookmarks

All Purchase Orders

Local Budget Data for Current Month

Local Non-Budget Data for Current Month

Outstanding POs Local (FIN-YEAR)

Outstanding POs Local (FIN-YEAR)

Common Actions

New Purchase Order

Save Purchase Order

Clear Changes

Change Status

Approve Purchase Order

Close Purchase Order

More Actions

Workflow

View History

Copy PR Line Items To PO

Create Contract

Complete Receipts

Revise PO

PO: ARL/2627 33333

Revision: 1

Site: ARLPWD

Status: APPR

Total Cost: 11,800.00

Term and Conditions

Sequence	Item	Description	Send to Vendor?
10	50L	Provision of Sales Tax Return (All)	✓
20	23L	Supply as per Order (all)	✓
30	2L	Copies of Invoice/Bill (all)	✓
40	4L	Company Right (all)	✓
50	5L	HSE requirements (all)	✓
60	15L	Loss on account of fluctuation of prices (all)	✓
70	14L	Income tax deduction (all)	✓
80	13L	Invoice sent (all)	✓
90	12L	Rejected Goods (all)	✓
100	11L	Not Part supplies bills (all)	✓
110	8L	Number of Purchase Orders (all)	✓
120	17L	Penalty (all)	✓
130	30	Delivery Chalan (all)	✓
140	34L	Delivery Timings (All)	✓
150	39L	Acknowledgement of Order (All)	✓

Select Terms New Row

How to Create a Purchase Order (PO)

A Purchase Order can be created from an existing Purchase Requisition by following these steps:

1. Open the required Purchase Requisition (PR).
2. From the Select Actions menu, select Create PO.
3. Enter a PO number or select Auto Number to let Maximo generate one.
4. Update the Description if required.
5. Click OK to create the purchase order.

Receiving Application

The Receiving application is used to record materials and services received against purchase orders. It allows users to receive ordered items as well as services provided by vendors or contractors.

To access the application, go to **Go To → Purchasing → Receiving**.

Receiving Application Tabs

- **List:** Used to search and view existing receiving records.
- **Material Receipts:** Used to record materials received against a purchase order. For inventory items, the received quantity is updated in inventory and an inventory transaction is generated.
- **Service Receipts:** Used to record services received from vendors or contractors against a purchase order, such as repair or maintenance services.

Receiving Materials and Services

The Receiving application allows both **materials and services** to be recorded when they are delivered or completed. Materials can be received as inventory items or as materials that are not tracked in inventory. Services can also be recorded based on the service provided by the vendor or contractor.

Invoices Application

An **invoice** is a bill received from a vendor for materials or services provided. The **Invoices** application is used to record vendor invoices and match their details with related purchase orders and receipts before sending them for approval and payment.

Required Invoice Information

The following information is required when creating an invoice:

1. **Invoice Number**
2. **Type**
3. **Entered Date**
4. **Entered By**
5. **Company**
6. **Currency**

Invoice Types

Maximo provides three main invoice types:

- **Invoice:** Used for normal payments to a vendor.
- **Credit:** Used when a credit is issued, such as for returned items.
- **Debit:** Used to record additional charges from a vendor.

Accessing the Invoices Application

The application can be opened from the Start Center or through:

Go To → Purchasing → Invoices

Invoices Application Tabs

- **List:** Used to search and view invoice records.
- **Invoice:** Used to create, view, and update invoices, credit notes, and debit notes.
- **Invoice Lines:** Used to enter and manage individual items or services included in an invoice.
- **Terms and Conditions:** Used to add or manage terms and conditions associated with the invoice.

Home
 Invoices

Advanced Search
 Save Query
 Bookmarks

Invoices
Filter >
1 - 20 of 34926

Invoice	Description	Status	Company / Contractor	Instl_Dept/Sec	Entered Date	WCh	PQ
1644	GAS NITROGEN (N2) COMMERCIAL GRADE FILLING PRESSURE 2000 PSI TO 2200 PSI	PAID	1977		9/29/08 12 28 PM		17692
1645	UNIFORM	PAID	5309		9/29/08 12:30 PM		ARL/1163
1646	BATTERY	PAID	1472		9/29/08 12:33 PM		18080
1647	SUZUKI PARTS	PAID	1952		9/29/08 12:37 PM		ARL/1120
1823	SHEZORE TRUCK	PAID	1952		11/7/08 9 44 AM		ARL/1390
1825	CV JOINT	PAID	1952		11/7/08 2 54 PM		ARL/1355
1841	PVC CABLE	PAID	1340		11/10/08 4 49 PM		18053
1842	FITTINGS	PAID	1956		11/10/08 4 57 PM		17930
1847	COMPRESSOR	PAID	1513		11/11/08 3 44 PM		ARL/1099
1848	ROTARY COMPRESSOR	PAID	1513		11/11/08 3 45 PM		ARL/1006
1896	HARDWARE ITEMS	PAID	2008		11/19/08 9 11 AM		ARL/1113
1908	STATIONARY	PAID	1345		11/20/08 10 57 AM		ARL/1419
1913	ELECTRICAL ITEMS	PAID	1445		11/21/08 9 01 AM		ARL/1362
1949	GENERAL ITEMS	PAID	1357		11/25/08 10 48 AM		ARL/1381
2058	CHEMICALS	PAID	1409		12/4/08 4 23 PM		ARL/1456
1543	TYRES	PAID	1665		9/29/08 11 29 AM		ARL/1241
1403	OIL ATTOCK SEO/APL ISO AW-680	PAID	5307		8/15/08 2 03 PM		18081

Invoices

Find Invoice

Find Navigation Item

List View | **Invoice** | Invoice Lines | Terms and Conditions | Specifications

Invoice: 1647 SUZUKI PARTS WO Num: Type: INVOICE Status: PAID
Site: ARLPWD Attachments

Invoice Details	PO Details	Dates
Original Invoice: PO: ARL/1120 Contract Reference: Entered Date: 9/29/08 12:37 PM		
Reverse Invoice: Site: ARLPWD Contract Type: Invoice Date:		
Vendor Invoice: Company: 1952 Contract Reference Revision: GL Posting Date: 7/15/13 2:09 PM		
Approval #: Currency: PKR Payment Schedule: Due Date:		
Entered By: 122460 Buyer: 113738 Paid Date:		
Dept/Section: Receipts: COMPLETE Total Cost: 11,755.00 Uninvoiced Total: 0.00		

Remit To

Contractor / Company: 1952 MEHMOOD AUTOS Check #: Pretax Total: 5,800.00

Address: Bank: Tax-1: 0.00

Contact: Bank Reference #: Tax-2: 0.00

Payment Terms: Phone: 051-5586514 Tax-3: 0.00

Check Code: Pay Tax to Vendor? Tax-4: 0.00

Tax-5: 0.00

Payment Details Filter > 0 - 0 of 0

INVENTORY MODULE


Inventory application

view

Managing your spare parts inventory is an important part of maintaining any asset. The Inventory module is used to manage spare parts inventory. The business goal is to find a balance of inventory stock, allowing maintenance work to be performed with minimum delays if materials are unavailable, but without keeping unnecessary or seldom used item in stock.

The Inventory module consists of the following applications:

1. Item Master
2. Service Items
3. Tools
4. Stocked Tools
5. Inventory
6. Issues and Transfers
7. Condition Codes
8. Storerooms



1. Item Master

The Item Master application is used to define items that will be stocked in your storerooms. When you create an item record, you define the possible attributes of the item, such as commodity codes, order and issue units, whether the item is lotted, rotating, or condition-enabled. With that, you also set any alternate items use in an item's place and a list of the condition codes you want applied to the item.


To access the application, select **go to** → **Inventory** → **Item Master**.

The Item Master application has the following tabs.

- **List:** Use this tab to search for item records. Although you may also use it to change status of multiple items, the tab has no other special action.
- **Item:** This tab is the main tab of the application. Use it to enter, view, or modify items.
- **Storerooms:** Use this tab to view a read-only list that has information about storerooms that stock the item. Examples are the costs and the balance for each storeroom.
To add an item to a storeroom, select Select Action → Add items to Storeroom
- **Vendors:** Use this tab to enter, view, modify, or delete information about vendors and manufacturers for an item. The list can include vendors that you have previously ordered from, and vendors that you have not purchased the item from. You may use the vendor data to compare prices and delivery information.
- **Specifications:** Use this tab to classify an item, and add, view, modify, or delete specifications that give details about the attributes of the item.

Item Assembly Structure: Use this tab to enter, view, or modify an item assembly structure). An IAS is a list of individual items and subassemblies that are required when you build an asset or define the requirements of a location. Rather than specify item components each time you enter an individual asset or a location, you create an item assembly structure as a template. You may use an IAS as a template when building multiple asset assembly structures and their related location systems.

List



The screenshot displays the IBM Item Master application interface. On the left is a navigation pane with sections like 'Find Navigation Item', 'Go To Applications', 'Available Queries', 'Common Actions', and 'More Actions'. The main area shows a table of items with columns: Item, Description, Commodity, Rotating?, KPI?, Condition Enabled?, and Status. The table lists various mechanical parts like nuts, washers, gaskets, and seals, all with a status of 'ACTIVE'.

Item	Description	Commodity	Rotating?	KPI?	Condition Enabled?	Status
729478	NUT LOCK & WASHER PINO 240 / 41 FOR INGERSOLL RAND PUMP 4 X 7	SPARES FOR PUMPS & GAS ENGINE	☐	☐	☒	ACTIVE
729484	WEAR RING IMPELLER (BACK), SEQ. # 004B FOR CENTRIFUGAL PUMP, MODEL 4 X 7 TAL. MAKE INGERSOLL RAND	SPARES FOR PUMPS & GAS ENGINE	☐	☐	☒	ACTIVE
729485	WEAR RING IMPELLER (FRONT), SEQ. # 004A FOR CENTRIFUGAL PUMP, MODEL 4 X 7 TAL. MAKE INGERSOLL RAND	SPARES FOR PUMPS & GAS ENGINE	☐	☐	☒	ACTIVE
849934	NUT LOCK BEARING 9602-10 N09 (Union)	HBUS & POWER PLANT SPARES	☐	☐	☒	ACTIVE
849794	SPRING 2047(Ingersoll rand)	HBUS & POWER PLANT SPARES	☐	☐	☒	ACTIVE
849908	GASKET PINO IR348104302	HBUS & POWER PLANT SPARES	☐	☐	☒	ACTIVE
848909	GASKET PINO IR348304302	HBUS & POWER PLANT SPARES	☐	☐	☒	ACTIVE
848910	GASKET PINO IR348404302	HBUS & POWER PLANT SPARES	☐	☐	☒	ACTIVE
848911	GASKET SPIRAL WOUND PINO IR348299282	HBUS & POWER PLANT SPARES	☐	☐	☒	ACTIVE
848914	PACKING SET PINO IR290201012	HBUS & POWER PLANT SPARES	☐	☐	☒	ACTIVE
848915	PIN GROOVE PINO IN322735072	HBUS & POWER PLANT SPARES	☐	☐	☒	ACTIVE
848916	PLUG BALL PINO IN657946172	HBUS & POWER PLANT SPARES	☐	☐	☒	ACTIVE
848919	RING BACKUP PINO IN659605292	HBUS & POWER PLANT SPARES	☐	☐	☒	ACTIVE
848920	RING SEAL PINO IN659705092	HBUS & POWER PLANT SPARES	☐	☐	☒	ACTIVE
848922	STEM PLUG PINO IU230535162	HBUS & POWER PLANT SPARES	☐	☐	☒	ACTIVE
848925	WIPER UPPER PINO IN672706332	HBUS & POWER PLANT SPARES	☐	☐	☒	ACTIVE
848933	DIAPHRAGM PINO IN798900082	HBUS & POWER PLANT SPARES	☐	☐	☒	ACTIVE

Item

Item Master

Find Item

Find Navigation Item

Go To Applications

Available Queries

All Records

All Bookmarks

Common Actions

More Actions

Item

Item Set: ITEMSET1

Commodity Group: HBUS & POWER PLANT SPARES

Commodity Code: SPRING

Meter Group:

Meter:

Lot Type: NOLDT

Maximum Quantity Issued:

Order Unit: NUMBER

Issue Unit:

MSDS:

Receipt Tolerance %:

Inspection Department:

Attachments

Status: ACTIVE

Rotating?:

Condition Enabled?:

K97:

Capitalized?:

Inspect on Receipt?:

Add as Spare Part?:

Attach to Parent Asset on Issue?:

Tax Exempt?:

Alternate Items

Condition Codes

Storerooms

Item Master

Find Item

Find Navigation Item

Go To Applications

Available Queries

All Records

All Bookmarks

Common Actions

More Actions

Item

Item Set: ITEMSET1

Commodity Group: HBUS & POWER PLANT SPARES

Commodity Code: SPRING

Meter Group:

Meter:

Lot Type: NOLDT

Maximum Quantity Issued:

Order Unit: NUMBER

Issue Unit:

MSDS:

Receipt Tolerance %:

Inspection Department:

Attachments

Status: ACTIVE

Rotating?:

Condition Enabled?:

K97:

Capitalized?:

Inspect on Receipt?:

Add as Spare Part?:

Attach to Parent Asset on Issue?:

Tax Exempt?:

Storeroom Information

Storeroom	Stock Category	Standard Cost	Average Cost	Last Receipt Cost	Unit of Measure	Unit Cost	Current Balance	Default Bin	Status	Site
HBUS/PP/SPV	STK	28.67	28.67	0.00			42.90	20-F-037	ACTIVE	ARLPWD

Vendors

Item Master

Find Item

Find Navigation Item

Go To Applications

Available Queries

All Records

All Bookmarks

Common Actions

More Actions

Item

Item Set: ITEMSET1

Commodity Group: HBUS & POWER PLANT SPARES

Commodity Code: SPRING

Meter Group:

Meter:

Lot Type: NOLDT

Maximum Quantity Issued:

Order Unit: NUMBER

Issue Unit:

MSDS:

Receipt Tolerance %:

Inspection Department:

Attachments

Status: ACTIVE

Rotating?:

Condition Enabled?:

K97:

Capitalized?:

Inspect on Receipt?:

Add as Spare Part?:

Attach to Parent Asset on Issue?:

Tax Exempt?:

Vendors

Vendor	Manufacturer	Model	Catalog #	Last Price	Last Order Date	Order Unit	Organization	Site
There are no rows to display.								

Specifications

Item Master

Find Item

Find Navigation Item

Go To Applications

Available Queries

All Records

All Bookmarks

Common Actions

New Item

Select Item

Clear Changes

Change Status

Create Report

More Actions

View Status History

Change Capitalized Status

Copy Item Assembly Structure

Add Items To Storeroom

Add Items To Multiple Storerooms

Unit of Measure and Conversion

View Contracts

Add/Modify Image

Item/Organization Details

Add/Modify Commodity Codes

Depreciation Schedule

List View

Item

Storerooms

Vendors

Specifications

Item Assembly Structure

Item 849794

SPRINGS 2047Z (Ingersoll Rand)

Classification

Class Description

Specifications

Filter

0 - 0 of 0

Attributes

Description

Data Type

Date Value

Alphanumeric Value

Numeric Value

Unit of Measure

Table Value

There are no rows to display.

New Row

Item Assembly Structure

Item Master

Find Item

Find Navigation Item

Go To Applications

Available Queries

All Records

All Bookmarks

Common Actions

New Item

Select Item

Clear Changes

Change Status

Create Report

More Actions

View Status History

Change Capitalized Status

Copy Item Assembly Structure

Add Items To Storeroom

Add Items To Multiple Storerooms

Unit of Measure and Conversion

View Contracts

Add/Modify Image

Item/Organization Details

Add/Modify Commodity Codes

Depreciation Schedule

Attachment Library/Folders

List View

Item

Storerooms

Vendors

Specifications

Item Assembly Structure

Top Level Item 849794

SPRINGS 2047Z (Ingersoll Rand)

Current Level

Belongs To

Remarks

Children

Filter

0 - 0 of 0

Item

Description

Quantity

Remarks

There are no rows to display.

New Row

MAXIMO ADMINISTRATION

MAXIMO ADMINISTRATION MODULE

The Administration module contains applications used to configure and manage different system-level settings and administrative information in Maximo.

The Administration module has the following applications:


- **Sets**
- **Organizations**
- **Calendars**
- **Resources**
- **Bulletin Board**
- **Communication Templates**
- **Report Administration**
- **Conditional Expression Manager**
- **Classifications**
- **CI Types**
- **Work View**
- **Organizations (Oil)**
- **Service Address**
- **Map Manager**
- **KPI**
- **Record Release**
- **Products (Oil)**
- **License Usage Monitor**
- **Administration**

1. Sets Application

The Sets application is used to manage and share item and company (vendor) information across multiple organizations. Before creating an organization, at least one Item Set and one Company Set must be created. Each organization is then linked to one item set and one company set. The same set can also be shared by multiple organizations, which helps maintain consistent item and vendor information across the system.

Types of Sets

1. **Item Sets:** Used to provide organizations with a common set of items and materials.
2. **Company Sets:** Used to maintain consistent vendor and company information across different organizations.



2. Organizations Application


The Organizations application is used to create and manage organizations and their associated sites in Maximo. At least one organization and one site must be defined for the system. For each organization, the following information can be configured:

- **Base Currency:** Defines the currency used by the organization.
- **Item and Company Sets:** Specifies the item and company sets associated with the organization.
- **Default Item Status:** Defines the default status assigned to items.
- **General Ledger Clearing Account:** Specifies the GL account used for clearing purposes.
- **Address Codes:** Used to manage addresses for organizational units and sites.


Using multiple organizations and sites allows different facilities to work within the same Maximo database while maintaining their own site-specific information and sharing common data where required.

This application has following tabs:


Organizations: Allows you to add, delete, view organizations information.



Addresses: Used to specify and manage physical mailing, billing, and shipping street addresses for the organization.



Sites: Used to define and manage specific operational sites belonging to the organization, including their active status, contacts, and default shipping and billing address assignments.



3. Calendar Application

The Calendar application is used to create and manage calendars that can be associated with different Maximo records, such as assets, labor, locations, preventive maintenance, and work orders.

A calendar defines working and non-working periods, including start and end dates, work shifts, and holidays. The same calendar can be assigned to multiple records, which helps maintain consistent working schedules across the system.

Calendars can be associated with:

- **Assets**
- **Labor**
- **Locations**
- **Organizations**
- **People**
- **Preventive Maintenance Records**
- **Service Level Agreements**
- **Tools**
- **Work Orders**

Calendars are generally created for organizations, but they can also be configured for specific sites when different facilities require different working schedules. Multiple calendars can be created when different working hours, shifts, or holidays need to be maintained.

This application has following tabs:

List: Use this tab to search for calendar records

Calendar	Description	Start Date	End Date	Organization
MORNING	Morning shift (general shift)	7/1/08	6/30/20	ARL
SHERICAL	TEST SHIF CAL	2/28/09	2/28/09	ARL
TESTICAL	FOR TESTING PURPOSE	7/10/08	7/31/08	ARL

Calendar: To view complete calendar including holidays and important events.

Sunday	Monday	Tuesday	Wednesday	Thursday	Friday	Saturday
1	2	3	4	5	6	7
8	9	10	11	12	13	14
15	16	17	18	19	20	21
22	23	24	25	26	27	28
29	30	31				

Work periods: To view complete work period including all the shifts.

Work Date	Shift	Sequence of Events Date	Start Time	End Time	Shift Hours	Notes
6/10/09	MORNING		8:00 AM	4:00 PM	8:00	
6/15/09	MORNING		8:00 AM	4:00 PM	8:00	
6/14/09	MORNING		8:00 AM	4:00 PM	8:00	
6/13/09	MORNING		8:00 AM	4:00 PM	8:00	
6/12/09	MORNING		8:00 AM	4:00 PM	8:00	
6/11/09	MORNING		8:00 AM	4:00 PM	8:00	
6/10/09	MORNING		8:00 AM	4:00 PM	8:00	
6/9/09	MORNING		8:00 AM	4:00 PM	8:00	
6/8/09	MORNING		8:00 AM	4:00 PM	8:00	
6/7/09	MORNING		8:00 AM	4:00 PM	8:00	
6/6/09	MORNING		8:00 AM	4:00 PM	8:00	
6/5/09	MORNING		8:00 AM	4:00 PM	8:00	