```
21-Mar-2024 10:56:13 {DSK}<home>larry>il>medley>internal>loadups>LOADUP-LISP.;4
 File created:
      edit by:
               1 mm
  changes to:
               (FNS LOADUP-LISP)
previous date:
               14-Mar-2024 12:16:33 {DSK}<home>larry>il>medley>internal>loadups>LOADUP-LISP.;3
 Read Table:
               XCL
    Package:
               INTERLISP
      Format:
                 XCCS
(RPAQQ LOADUP-LISPCOMS ((FNS LOADUP-LISP)
                            (INITVARS (FILING.ENUMERATION.DEPTH 1))
                            (FILES MEDLEYDIR)
                            (GLOBALVARS MAKESYSFILENAME MEDLEY-INIT-VARS MEDLEYDIR SYSTEMINITVARS USERRECLST)))
(DEFINEQ
(LOADUP-LISP
                                                                        Edited 21-Mar-2024 10:55 by Imm
  (LAMBDA (DRIBBLEFILE)
                                                                         Edited 14-Mar-2024 12:16 by Imm
                                                                         Edited 26-Feb-2023 12:17 by lmm
                                                                        ; Edited 13-Jul-2022 14:09 by rmk
; Edited 4-Mar-2022 19:13 by larry
; Edited 29-Apr-2021 22:30 by rmk:
    (SETQQ COMPILE.EXT LCOM)
    (MEDLEY-INIT-VARS)
                                                                        ; should be set earlier
     (DRIBBLE DRIBBLEFILE)
    (FOR X IN BOOTLOADEDFILES DO (CL:UNLESS (MEMB X SYSFILES)
                                          (PRINTOUT T X " bootloaded" T)
                                          (SETQ SYSFILES (CONS X SYSFILES))))
     (SETO BOOTLOADEDFILES NIL)
        (NOT (BOUNDP 'DIRECTORIES))
         THEN (SETQ DIRECTORIES LOADUPDIRECTORIES))
    ;; following files are really loaded earlier, this call to LOADUP just cleans up
    (LOADUP ' (ACODE MACHINEINDEPENDENT))
    ;; establish all package exports early
    (LOADUP '(LISP-PACKAGE FASL-PACKAGE D-ASSEM-PACKAGE COMPILER-PACKAGE))
    ;; load FASL loader here, so we can load DFASLs earlier in loadup
    (LOADUP '(ERROR-RUNTIME CMLARITH CONDITION-HIERARCHY CMLHASH D-ASSEM FASLOAD))
    ;; These are needed by any FASL files
    (LOADUP '(DEFFER-RUNTIME CMLPRINT CLSTREAMS CMLSTRING CMLSYMBOL CMLTYPES CMLSEQCOMMON CMLSEQMAPPERS
                      CMLPATHNAME CMLFILESYS))
;;; * 'FASL files may be loaded after this point' * * *
    (LOADUP '(CMLDEFFER ERROR-RUNTIME-AFTER-FASL WRAPPERS))
    ;; early runtime support for Common Lisp and (temporarily) debugger
    (LOADUP '(STACKFNS CMLMVS MACROS MACROAUX UNWINDMACROS))
    (LOADUP ' (COMMON XCLC-RUNTIME CMLTYPES CL-ERROR))
    (LOADUP '(AFONT EDIT WEDIT PRETTY DSPRINTDEF NEWPRINTDEF FONTPROFILE SPELLFILE PRINTFN LOADFNS DMISC
                      DIRECTORY SPELLFILE FILEPKG RESOURCE))
    ;; needed for makesys
    ;; The Byte Compiler (DLAP, BYTECOMPILER, COMPILER) used to be here. Moved after XCL Compiler so that one byte compiler init will work.
    ;; JDS 10/11/89
    (LOADUP '(HIST UNDO SPELL DWIM WTFIX CLISP DWIMIFY CLISPIFY RECORD))
    (LOADUP ' (GAINSPACE COROUTINE ARGLIST ASKUSER SYSPRETTY COMMON COMPARE))
    (DWIM 'C)
    ;; Kernel Common Lisp files
    (LOADUP '(CMLSTEP CMLDOC CMLPARSE CMLSETF CMLPRED CMLREAD WALKER CMLSEQFINDER CMLSEQMODIFY CMLSORT DEFSTRUCT
                      CMLMISCIO CMLCOMPILE CMLDESTRUCT CL-ERROR CMLFORMAT CMLENVIRONMENT CMLLOAD CMLFLOAT CMLTIME
                      CMLRAND CMLMODULES))
    (LOADUP '(PROFILE CMLEXEC EXEC-COMMANDS DEBUGGER IL-ERROR-STUFF DEBUGEDIT))
    (LOADUP '(ADDARITH))
    (LOADUP ' (UNICODE CMLPATHNAME HPRINT AARITH ADISPLAY HLDISPLAY MENU WINDOWOBJ WINDOWSCROLL WINDOW WINDOWICON
                      PAINTW ATTACHEDWINDOW XXGEOM XXFILL DEXEC INSPECT DESCRIBE CMLARRAYINSPECTOR EDITINTERFACE
                      TTYIN))
    (LOADUP '(BREAK-AND-TRACE))
    (LOADUP '(FASDUMP XCL-COMPILER ADVISE))
    ;; the bytecompiler and Interlisp compiler interface functions
    (LOADUP '(DLAP BYTECOMPILER COMPILE))
    (LOADUP '(DSK UFS UFSCALLC MAIKOBITBLT))
     (LOADUP '(TIME))
    (LOADUP '(BRKDWN))
     (LOADUP '(LOGOW IDLER HARDCOPY ICONW FREEMENU SEDIT))
    (LOADUP '(XCL-EXTRAS))
```

```
;; CMLPACKAGE pushes onto INSPECTMACROS
    (LOADUP '(CMLPACKAGE))
    ;; Puts ARGNAME properties on CL and XCL functions that IL:SMARTARGLIST can't hack. Keep this last so everything will be defined when it
    ;; runs
    (LOADUP '(CMLSMARTARGS))
    (LOADUP '(IMPLICIT-KEY-HASH CLOSURE-CACHE))
    ;; not sure what this depends on, so putting it here
    (LOADUP '(BIGBITMAPS))
    ;; Already enabled, but this time fixes tables that weren't defined in the init
    (PACKAGE-ENABLE)
    ;; Added late, LOAD late to avoid any dependencies
    (LOADUP '(XCL-LOOP XCL-HASH-LOOP))
    ;; networking code -- should make it optional but too many cross dependencies
    (LOADUP '(PUP 10MBDRIVER LEAF LLETHER DPUPFTP LOCALFILE DSKDISPLAY COURIER LLNS TRSERVER SPP NSPRINT
                    AUTHENTICATION BSP CLEARINGHOUSE NSFILING MAIKOETHER))
    (DRIBBLE)
    (SETQ MAKESYSNAME :MEDLEY)))
(RPAQ? FILING.ENUMERATION.DEPTH 1)
(FILESLOAD MEDLEYDIR)
(DECLARE\: DOEVAL@COMPILE DONTCOPY
(GLOBALVARS MAKESYSFILENAME MEDLEY-INIT-VARS MEDLEYDIR SYSTEMINITVARS USERRECLST)
```

{MEDLEY}<internal>loadups>LOADUP-LISP.;1 28-Jun-2024 18:34:03 -- Listed on 30-Jun-2024 13:22:36 --

FUNCTION INDEX
LOADUP-LISP1
VARIABLE INDEX
FILING.ENUMERATION.DEPTH2