```
27-Jan-89 10:23:15 {DSK}<LISPFILES>MICROTEK>MICROTEKPRINT.;1
 File created:
  changes to:
                (FNS MT.CREATEPRINTMASTER)
previous date:
               23-Jul-88 15:18:48 {ERINYES}<IJSP>MEDIEY>IJSPUSERS>MICROTEKPRINT.:1
 Read Table:
               INTERLISP
    Package:
               INTERLISP
       Format:
                 XCCS
"; Copyright (c) 1986, 1987, 1988, 1989 by XEROX Corporation. All rights reserved.
(RPAQQ MICROTEKPRINTCOMS
        [(P (FILESLOAD MICROTEK))
         (FNS MT.PRINT.MENU MT.GETXPOS MT.GETYPOS MT.CREATEPRINT MT.CREATEPRINTMASTER MT.SELECT.SCALEFACTOR)
(P (IF (AND (BOUNDP 'MT.DISPLAY.MENUWINDOW)
                       (OPENWP MT.DISPLAY.MENUWINDOW))
                 THEN
                 (MT.PRINT.MENUl)
(FILESLOAD MICROTEK)
(DEFINEO
(MT.PRINT.MENU
                                                                         ; Edited 21-May-87 09:23 by ronald clarke:xsis:xerox
  [LAMBDA NIL
    (PROG (MENU.DESCRIPTION)
           [SETQ MENU.DESCRIPTION
             '(((PROPS ID MPRINT)
                       (PROPS FORMAT EXPLICIT COORDINATES GROUP BACKGROUND 23130)
(TYPE MOMENTARY LABEL "PRINT" BOX 3 LEFT 0 BOTTOM 2 FONT (MODERN 12 BOLD)
                              SELECTEDFN MT.CREATEPRINT)
                        (TYPE STATE LABEL "Printer!: " ID PRINTERTYPE MENUITEMS (8044 4045)
                              INITSTATE 8044 LINKS (DISPLAY (GROUP PRINTER))
                              FONT
                              (MODERN 10 BOLD)
                              BOX 1 LEFT 60 BOTTOM 3)
                        (TYPE DISPLAY ID PRINTER LABEL "" LEFT 115 BOTTOM 3 BOX 1 MAXWIDTH 30)
                        (TYPE MOMENTARY LABEL "XPOS!: " SELECTEDFN MT.GETXPOS FONT (MODERN 10 BOLD)
LEFT 175 BOTTOM 3 BOX 1)
                        (TYPE EDIT ID XPOS LABEL 0 MAXWIDTH 45 LEFT 220 BOTTOM 3 BOX 1)
                        (TYPE MOMENTARY LABEL "YPOS!: " SELECTEDFN MT.GETYPOS FONT (MODERN 10 BOLD)
                        LEFT 280 BOTTOM 3 BOX 1)
(TYPE EDIT ID YPOS LABEL 0 MAXWIDTH 45 LEFT 325 BOTTOM 3 BOX 1)
                        (TYPE MOMENTARY LABEL "SCALE!: " FONT (MODERN 10 BOLD)
LEFT 385 BOTTOM 3 BOX 1 SELECTEDFN MT.SELECT.SCALEFACTOR)
                        (TYPE EDIT LABEL "1:1" ID SCALEFACTOR LEFT 435 BOTTOM 3 BOX 1]
           (SETQ MT.PRINT.MENUWINDOW (FREEMENU MENU.DESCRIPTION "Microtek Print Menu" 23130 5))
           (OPENW MT.PRINT.MENUWINDOW)
           (ATTACHWINDOW MT.PRINT.MENUWINDOW MT.DISPLAY.MENUWINDOW 'BOTTOM 'JUSTIFY])
(MT.GETXPOS
                                                                         ; Edited 21-May-87 09:15 by ronald clarke:xsis:xerox
  [LAMBDA NIL
    (FM.EDITITEM (FM.GETITEM 'XPOS NIL MT.PRINT.MENUWINDOW)
            MT.PRINT.MENUWINDOW1)
(MT.GETYPOS
  [LAMBDA NIL
                                                                         ; Edited 21-May-87 09:17 by ronald clarke:xsis:xerox
    (FM.EDITITEM (FM.GETITEM 'YPOS NIL MT.PRINT.MENUWINDOW)
            MT.PRINT.MENUWINDOW])
(MT.CREATEPRINT
  [LAMBDA NIL
                                                                         ; Edited 21-May-87 09:29 by ronald clarke:xsis:xerox
    (PROG NIL
           (if (AND [BOUNDP (SETQ BITMAP (MKATOM (LISTGET (FM.GETSTATE MT.DISPLAY.MENUWINDOW)
                                                             'BITMAPNAME]
                     (BITMAPP (SETQ BITMAP (EVAL BITMAP)))
                     (if (OR [AND (EQ (MKATOM (LISTGET (FM.GETSTATE MT.PRINT.MENUWINDOW)
                                                       'PRINTERTYPE))
                                  (FMEMB (MKATOM (LISTGET (FM.GETSTATE MT.PRINT.MENUWINDOW)
                                                           'SCALEFACTOR))
                                          '(4%:1 2%:1 1%:1 1%:2 1%:4]
                            (EQ (MKATOM (LISTGET (FM.GETSTATE MT.PRINT.MENUWINDOW)
                                                  'PRINTERTYPE))
                                 8044))
                        then T
                      else (FLASHWINDOW MT.STATUSWINDOW 3)
                            (MT.PRINT.STATUS "Not a valid scale for 4045 printer")
                           (RETURN NIL)))
```

```
then (MT.PRINT.STATUS ""
                     [MT.CREATEPRINTMASTER BITMAP (MKATOM (LISTGET (FM.GETSTATE MT.PRINT.MENUWINDOW)
                                                                        'XPOS))
                             (MKATOM (LISTGET (FM.GETSTATE MT.PRINT.MENUWINDOW)
                                             'YPOS))
                             (MKATOM (LISTGET (FM.GETSTATE MT.PRINT.MENUWINDOW)
                                             'SCALEFACTOR]
             else (FLASHWINDOW MT.STATUSWINDOW 3)
                  (MT.PRINT.STATUS "This atom is not a bitmap")
                  (RETURN NIL])
(MT.CREATEPRINTMASTER
  [LAMBDA (BITMAP X Y SCALEFACTOR)
                                                                        ; Edited 27-Jan-89 10:21 by rclarke.pa
    (PROG (IPS SCANFACTOR SCALE)
           [if (EQP (LISTGET (FM.GETSTATE MT.PRINT.MENUWINDOW)
                            'PRINTERTYPE)
                   8044)
               then (if [NOT (SETQ SCANFACTOR
                               (LISTGET '(0 0.24 5 0.252 10 0.266 15 0.282 20 0.3 25 0.32 33 0.36 35 0.369 40 0.4 45 0.439 50 0.48 55 0.533 60 0.6 67 0.7200001 70 0.8 75 0.96) (GETPROP (MKATOM (LISTGET (FM.GETSTATE MT.DISPLAY.MENUWINDOW)
                                                                  'BITMAPNAME))
                                              'RESOLUTION]
                         then (MT.PRINT.STATUS "")
                               (FLASHWINDOW MT.STATUSWINDOW 3)
                              (if [NOT (NUMBERP (SETQ SCANFACTOR (MKATOM (PROMPTFORWORD "Resolution not on Bitmap proplist. Enter #:" "1" NIL
                                                                                     MT.STATUSWINDOW1
                                  then (FLASHWINDOW MT.STATUSWINDOW 2)
    (MT.PRINT.STATUS "This is not a number")
                              (RETURN NIL))
(MT.PRINT.STATUS ""))
                    [SETQ SCALE (FQUOTIENT (CAR (UNPACK SCALEFACTOR))
                                          (CADDR (UNPACK SCALEFACTOR)
                     (SETQ IPS (OPENIMAGESTREAM '{LPT}.IP))
                     (SCALEDBITBLT BITMAP 0 0 IPS X Y 21590 27940 'INPUT 'REPLACE NIL '(0 0 21590 27940)
                            (FTIMES SCALE SCANFACTOR))
             else (if [NOT
                           (SETQ SCANFACTOR
                            (LISTGET '(0 1 5 1 10 1 15 1 20 1 25 1 33 1 35 1 40 2 45 2 50 2 55 2 60 2 67 4 70 4 75
                                           4)
                                    (GETPROP (MKATOM (LISTGET (FM.GETSTATE MT.DISPLAY.MENUWINDOW)
                                                               'BITMAPNAME))
                                            'RESOLUTION]
                      then (MT.PRINT.STATUS "")
                            (FLASHWINDOW MT.STATUSWINDOW 3)
                            (if [NOT (NUMBERP (SETQ SCANFACTOR (MKATOM (PROMPTFORWORD "Resolution not on Bitmap
                                                                                   proplist. Enter #:" "1" NIL
                                                                                   MT.STATUSWINDOW)
                                then (FLASHWINDOW MT.STATUSWINDOW 2)
                                     (MT.PRINT.STATUS "This is not a number")
                                     (RETURN NIL))
                            (MT.PRINT.STATUS ""))
                  [SETQ SCALE (FQUOTIENT (CAR (UNPACK SCALEFACTOR))
                  (CADDR (UNPACK SCALEFACTOR]
(SETQ IPS (OPENIMAGESTREAM '{LPT}.4045XLP))
                  (if (GREATERP (FTIMES SCALE SCANFACTOR)
                             4)
                      then (FLASHWINDOW MT.STATUSWINDOW 2)
     (MT.PRINT.STATUS "Not a valid scale for reduction used on this bitmap")
                            (RETURN NIL))
                  (SCALEDBITBLT BITMAP 0 0 IPS X Y 2550 3300 'INPUT 'REPLACE NIL '(0 0 2550 3300)
                          (FIXR (FTIMES SCALE SCANFACTOR]
           (CLOSEF IPS)
           (MT.PRINT.STATUS "Bitmap sent to printer"])
(MT.SELECT.SCALEFACTOR
  [LAMBDA NIL
                                                                        ; Edited 21-May-87 09:26 by ronald clarke:xsis:xerox
    (PROG [(PRINTERTYPE (LISTGET (FM.GETSTATE MT.PRINT.MENUWINDOW)
                                  'PRINTERTYPE]
           [if (EQP PRINTERTYPE 8044)
               then (SETQ FACTORS
                      '(8$:1 7%:1 6%:1 5%:1 4%:1 3%:1 2%:1 1%:1 1%:2 1%:3 1%:4 1%:5 1%:6 1%:7 1%:8))
             else (SETQ FACTORS '(4%:1 2%:1 1%:1 1%:2 1%:4]
           (FM.CHANGESTATE (FM.GETITEM 'SCALEFACTOR NIL MT.PRINT.MENUWINDOW)
                   (MENU (create MENU
                                 ITEMS _ FACTORS))
                  MT.PRINT.MENUWINDOW])
(IF (AND (BOUNDP 'MT.DISPLAY.MENUWINDOW)
         (OPENWP MT.DISPLAY.MENUWINDOW))
    THEN (MT.PRINT.MENU))
(PUTPROPS MICROTEKPRINT COPYRIGHT ("XEROX Corporation" 1986 1987 1988 1989))
```


FUNCTION INDEX		
	MT.GETXPOS	