```
7-Jun-93 15:34:58 {DSK}ct>medley2.0>lispusers>SETDEFAULTPRINTER.;7
 File created:
  changes to:
                (VARS SETDEFAULTPRINTERCOMS)
                (FNS \sdp.menu.subitems)
previous date:
                29-May-93 15:44:06 {DSK}column{pmay.09}15:44:06 {DSK}column{pmay.09}15:44:06 {DSK}column{pmay.09}15:44:06
 Read Table:
                TNTERLISP
    Package:
                INTERLISP
       Format:
                 XCCS
", Copyright (c) 1985, 1986, 1987, 1993 by Xerox Corporation. All rights reserved.
(RPAQQ SETDEFAULTPRINTERCOMS
;;; the regular DEFAULTSUBITEMFN modified to recognize EVAL as a key to EVAL the CADR of the list to get the subitems
         (FILES DEFAULTSUBITEMFN)
;;; the setdefaultprinter functions
         (FNS \sdp.menu.subitems \sdp.set.printer)
;;; SDP.PRINTERINFO is the place to look up things like printer location, it also looks on the name of the printer for a LOCATION property
         (INITVARS (SDP.PRINTERINFO NIL))
;;; insinuate self into background menu
         [ADDVARS (BackgroundMenuCommands ("Set Default Printer" (\sdp.set.printer (GetNewPrinterFromUser))
                                                        "Asks for (new) default printer name.
                                                                                                    <cr> without entering
                                                        name aborts change."
                                                        (EVAL (\sdp.menu.subitems]
;;; reset the background menu so our change takes effect, and remove space from the separators when reading printer names
         (P (SETO BackgroundMenu))))
;;; the regular DEFAULTSUBITEMFN modified to recognize EVAL as a key to EVAL the CADR of the list to get the subitems
(FILESLOAD DEFAULTSUBITEMFN)
;;; the setdefaultprinter functions
(DEFINEQ
(\sdp.menu.subitems
                                                                           ; Edited 7-Jun-93 15:30 by rmk:
  [LAMBDA NIL
                                                                           (* N.H.Briggs "24-Mar-86 16:09")
ST (IF (NIEN P)
     (NCONC1 [FOR P PNAME INSIDE DEFAULTPRINTINGHOST COLLECT (LIST
                                                                                   THEN P
                                                                                ELSEIF (CADDR P)
THEN (CONCAT (CADR P)
                                                                                                  (CADDR P))
                                                                                ELSE (CADR P))
                                                                               (LIST '\sdp.set.printer (KWOTE P))
                                                                               (OR (GETPROP (U-CASE P)
                                                                                           'LOCATION)
                                                                                   (CDR (ASSOC (U-CASE P)
                                                                                                 SDP.PRINTERINFO]
             (LIST "Other..." '(\sdp.set.printer (GetNewPrinterFromUser))
                    "Asks for (new) default printer name. <cr> without entering name aborts change."])
(\sdp.set.printer
  [LAMBDA (PRINTER)
                                                                           ; Edited 29-May-93 15:11 by rmk:
                                                                           (* N.H.Briggs " 8-Jul-86 12:29")
    ;; CANONICAL.HOSTNAME is NIL except for XNS hosts
     (SETQ DEFAULTPRINTINGHOST (MKLIST DEFAULTPRINTINGHOST))
        PRINTER
         THEN
               ;; Convert to canonical name
                (SETO PRINTER (IF
                                    (LISTP PRINTER)
                                    THEN (LIST (CAR PRINTER)
```

```
(OR (CANONICAL.HOSTNAME (CADR PRINTER))
                                                  (CADR PRINTER))
                                              (CADDR PRINTER))
                               ELSE (OR (CANONICAL.HOSTNAME PRINTER)
                                         PRINTER)))
              (LET ((TOP (CAR DEFAULTPRINTINGHOST))
                     (CANONICALPRINTERNAME (IF (LISTP PRINTER)
                                                THEN (CADR PRINTER)
                                              ELSE PRINTER)))
                    (IF (IF
                           (LISTP PRINTER)
                           THEN [AND (LISTP TOP)
                                       (EQ (CAR TOP)
                                           (CAR PRINTER))
                                          (CADDR TOP)
                                           (CADDR PRINTER))
                                       (STRING-EQUAL CANONICALPRINTERNAME (OR (CANONICAL.HOSTNAME (CADR TOP))
                                                                                (CADR TOP)
                         ELSE (AND (NLISTP TOP)
                                    (STRING-EQUAL (OR (CANONICAL.HOSTNAME TOP)
                                                       TOP)
                     (CAR PRINTER))
                                                                      (EQ (CADDR P)
                                                                           (CADDR PRINTER))
                                                                      (STRING-EQUAL CANONICALPRINTERNAME
                                                                              (OR (CANONICAL.HOSTNAME (CADR P))
                                                                                  (CADR P]
                                                        COLLECT P)
                                             ELSE (FOR P IN DEFAULTPRINTINGHOST UNLESS (AND (NLISTP P)
                                                                    (STRING-EQUAL CANONICALPRINTERNAME
                                                                           (OR (CANONICAL.HOSTNAME P)
                                                                               P)))
                                                      COLLECT P]
                           (PROMPTPRINT "default printer set to " PRINTER]
    NIL])
)
;;; SDP.PRINTERINFO is the place to look up things like printer location, it also looks on the name of the printer for a LOCATION property
(RPAO? SDP.PRINTERINFO NIL)
;;; insinuate self into background menu
(ADDTOVAR BackgroundMenuCommands ("Set Default Printer" (\sdp.set.printer (GetNewPrinterFromUser))
                                           "Asks for (new) default printer name. <cr> without entering name aborts change."
                                            (EVAL (\sdp.menu.subitems))))
;;; reset the background menu so our change takes effect, and remove space from the separators when reading printer names
(SETQ BackgroundMenu)
(PUTPROPS SETDEFAULTPRINTER COPYRIGHT ("Xerox Corporation" 1985 1986 1987 1993))
```

{MEDLEY}spusers>SETDEFAULTPRINTER.;1 28-Jun-2024 18:34:03 -- Listed on 30-Jun-2024 13:14:52 --

FUNCTION INDEX	
\sdp.menu.subitems	\sdp.set.printer1
VARIABL	E INDEX
BackgroundMenuCommands2	SDP.PRINTERINFO