Icone Iron Pro Plugins Internet Installer (AutoInstaller), Installation Guide

By farhamxp@gmail.com

In this guide, selection means: select custom object then press Ok on remote.

Note: The device must be connected to the Internet at all states.

Important Notes:

- AutoInstaller just run with \$scripter_2.4signed.apk available in AutoInstaller repository. if anyone use another version of scripter, we aren't support them and the development team has no responsibility.
- Each downloaded plugin file, stored in plugin folder on the sdcard (/sdcar/plugin).
- All Plugins files directly downloadable from https://github.com/IronAutoPlugin/Iron-Plugins . If custom plugin not found in plugins repository, please tell us.
- Contact information, License and develop team information are available on 0_About_AutoInstaller.



- 1- Go to AutoInstaller repository (https://github.com/IronAutoPlugin/AutoInstaller) and download these files. After download, must have this files:
 - a. Scripts runner app (\$scripter_2.4signed.apk)
 - b. AutoInstaller Plugin (AIP.tar)
 - c. Installer script (0_AutoInstaller_Install)
 - d. Main Files (IAP.tar)



2- Transfer all of these files to root folder of Internal storage (sdcard)





3- Install \$scripter_2.4signed.apk on your device and then run it. If there was any other version of \$cripter app, uninstall them, before installing \$scripter_2.4signed.apk.




4- After running \$cripter app, you seen 0_AutoInstaller_Install. Select it and then run it with Ok on the remote.



After running installer script, you see this message. Select Close and then press Ok on the remote and close app with Exit key on the remote.

5- Go to Plugin section and select AutoInstaller plugin. then start it with remote green key. If all files copied correctly and last steps execute correctly, AutoInstaller plugin will removed from plugin list and install successfully.



6- Exit from plugin section and run \$cripter app again. In second run, you see this.




Items In main menu:

- O About AutoInstaller: describe AutoInstaller
- 1_Install_Reinstall_AutoInstaller: Install or reinstall AutoInstaller when there was a problem in run scripts. Don't use it on normal mode.
- 2_Upgrade_AutoInstaller: upgrade AutoInstaller from its repository.


 If there is new upgrade of AutoInstaller, its news will publish in news channel. Also it was check installed version with repository version before upgrade to new version.
- 3_Start_FTP_service: start ftp (file transfer protocol) service. After starting service, /sdcard available in local network with full permission(read/write) and without any user and password.
- 4_Stop_FTP_service: stop ftp service.
- 5_AutoPlugin_Local_Install: if there is plugin files in /sdcard/plugin, and its format same as repository plugins, you can install them with this optin.
- 6_AutoPlugin_Update_list: update latest plugin list from repository. It's better run this option before install any plugin to update plugin list.
- 7_AutoPlugin_Update_Archivelist: update plugin list from archive repository. It's better run this option before install any plugin from archive to update archived plugin list.
- 8_AutoPlugin_ShowList: shows updated latest plugin list.
- 9_AutoPlugin_ShowArchiveList: shows updated archive plugin list.

7- Select 6_AutoPlugin_Update_list and run it.



After some seconds, the list of available plugin in the server, will update in device.


8- Select 8_AutoPlugin_ShowList to shows updated latest plugin list.



9- Select and run 7_AutoPlugin_Update_Archivelist and then select and run 9_AutoPlugin_ShowArchiveList to shows updated archive plugin list.

10- Select your custom plugin installer and run it, then Close the message window. (For example Ncam10499_STAPI_MNASR)





Note: For each plugin installation, you must repeat step 10. After running all custom plugins installer, you can change plugins settings (start/stop or startup mode) from plugin section.