

LINUX SERWER (UBUNTU) SAMBA

Niebieski kolor czcionki -> komentarz działania

Czarny kolor czcionki -> polecenia

sudo su {haslo}

zalogowanie na root

ls

listuje pliki

cd home

mkdir {nazwa_katalogu}

cd /etc

przejsć do katalogu /etc

ls

cd samba

ls

sudo nano smb.conf

```
GNU nano 2.2 smb.conf
# users profiles (see the "login path" option above)
# (you need to configure Samba to act as a domain controller too.)
# The path below should be writable by all users so that their
# profile directory may be created the first time they log on
[profiles]
; comment = Users profiles
; path = /home/samba/profiles
; guest ok = no
; browseable = no
; create mask = 0600
; directory mask = 0700

[printers]
comment = All Printers
browseable = no
path = /var/tmp
printable = yes
guest ok = no
read only = yes
create mask = 0700

# Windows clients look for this share name as a source of downloadable
# printer drivers
[print$]
comment = Printer Drivers
path = /var/lib/samba/printers
browseable = yes
read only = yes
guest ok = no
# Uncomment to allow remote administration of Windows print drivers.
# You may need to replace 'lpadmin' with the name of the group your
# admin users are members of.
# Please note that you also need to set appropriate Unix permissions
# to the drivers directory for these users to have write rights in it
; write list = root, @lpadmin

[EGZAMIN]
comment = Uczyimy się do egzaminu
path = /home/egzamin2
guest ok = yes
browseable = yes
read only = no

^C Help      ^O Write Out  ^W Where Is   ^X Cut        ^E Execute    ^L Location   ^U Undo       ^M Set Mark   ^_ To Bracket  ^P Previous   ^B Back
^X Exit      ^R Read File  ^N Replace    ^V Paste      ^J Justify    ^G Go To Line ^R Redo       ^C Copy       ^H Where Was  ^M Next       ^F Forward
```

LINUX SERWER (UBUNTU) SAMBA

KONFIGURACJA SAMBA DLA DOMYŚLNEGO UŻYTKOWNIKA (ROOT) !!!

sudo **smbpasswd** -a **ustalenie hasła dla root do SAMBY**

Podajemy hasło, następnie je potwierdzamy. Przy logowaniu się do udziału. Użytkownika podjemy jako **root**, a hasło które nadaliśmy do usługi poleceniem **smbpasswd**

KONFIGURACJA SAMBA DLA DODATKOWEGO UŻYTKOWNIKA

sudo adduser nazwa_uzytkownika **tworzenie uzytkownika**


sudo smbpasswd -a nazwa_uzytkownika **dodanie uzytkownika do usługi samba**

sudo systemctl restart smb **restart usługi samba**

sudo systemctl status smb **sprawdzenie statusu usługi(działania) samba**

SPRAWDZENIE DZIAŁANIA USŁUGI SAMBA NA WINDOWS

Win + r \\{adres_serwera_LINUX}



LINUX SERWER (UBUNTU) SAMBA

