

LINUX SERWER (UBUNTU) SSH

SSH domyślnie pracuje na porcie 22.

Niebieski kolor czcionki -> komentarz działania

Czarny kolor czcionki -> polecenia

Sudo su {hasło}

zalogowanie na root

Ls

listuje pliki

Cd /etc


przejsć do katalogu

Ls

Cd ssh

Ls

Nano sshd_config edytowanie pliku aby zmienić port usługi SSH, należy usunąć #, i zmienić numer portu.



```
GNU nano 7.2 sshd config
# This is the sshd server system-wide configuration file. See
# sshd_config(5) for more information.
# This sshd was compiled with PATH=/usr/local/sbin:/usr/local/bin:/usr/sbin:/usr/bin:/sbin:/bin:/usr/games
# The strategy used for options in the default sshd_config shipped with
# OpenSSH is to specify options with their default value where
# possible, but leave them commented. Uncommented options override the
# default value.
Include /etc/ssh/sshd_config.d/*.conf
# When systemd socket activation is used (the default), the socket
# configuration must be re-generated after changing Port, AddressFamily, or
# ListenAddress.
#
# For changes to take effect, run:
#
#   systemctl daemon-reload
#   systemctl restart ssh.socket
#
#Port 22
#AddressFamily any
#ListenAddress 0.0.0.0
#ListenAddress ::

#HostKey /etc/ssh/ssh_host_rsa_key
#HostKey /etc/ssh/ssh_host_ecdsa_key
#HostKey /etc/ssh/ssh_host_ed25519_key

# Ciphers and keying
#RekeyLimit default none

# Logging
#SyslogFacility AUTH
#LogLevel INFO

[ Read 131 lines ]
^G Help      ^O Write Out ^W Where Is  ^K Cut       ^_ Execute   ^C Location M-U Undo      M-A Set Mark M-_ To Bracket M-Q Previous
^X Exit      ^R Read File ^N Replace   ^P Paste     ^J Justify  ^V Go To Line M-R Redo     M-E Copy     ^Q Where Was M-W Next
```

Po zmianie Portu, należy zrestartować naszą usługę

Sudo systemctl restart ssh

restart usługi SSH


Sudo systemctl status ssh

sprawdzenie

statusu(działania) usługi SSH

LINUX SERWER (UBUNTU) SSH

SPOSOBY PODŁĄCZENIA SIĘ ZA POMOCĄ USŁUGI SSH

A screenshot of a Windows command prompt window. The title bar shows 'C:\WINDOWS\system32\cmd.exe'. The window contains the following text: '(c) Microsoft Corporation. Wszelkie prawa zastrzeżone.' followed by a new line, and then the command 'C:\Users\Yaro>ssh gf@192.168.10.100 -p 2222'.

ssh nazwa_użytkownika@adresIP -p numer_portu

ssh- nazwa usługi

nazwa_użytkownika- nazwa użytkownika za pomocą którego chcemy się zalogować

adresIP- adres IPv4 urządzenia do którego chcemy się dostać

parametr -p [numer_portu] wskazuje na wybrany port, na którym pracuje nasza usługa

LINUX SERWER (UBUNTU) SSH

SPRAWDZENIE DZIAŁANIA NASZEJ USŁUGI NA WINDOWS CLIENT

```
gf@gf: ~  
Microsoft Windows [Version 10.0.19045.6466]  
(c) Microsoft Corporation. Wszelkie prawa zastrzeżone.  
  
C:\Users\Yaro>ssh gf@192.168.10.100 -p 2222  
The authenticity of host '[192.168.10.100]:2222 ([192.168.10.100]:2222)' can't be established.  
ED25519 key fingerprint is SHA256:fz7mcc1MOg5cgomVB6KGz0uva28aBL6GPYZFNworbDo.  
This host key is known by the following other names/addresses:  
C:\Users\Yaro/.ssh/known_hosts:5: [192.168.10.250]:1000  
Are you sure you want to continue connecting (yes/no/[fingerprint])? yes  
Warning: Permanently added '[192.168.10.100]:2222' (ED25519) to the list of known hosts.  
gf@192.168.10.100's password:  
Welcome to Ubuntu 24.04.4 LTS (GNU/Linux 6.8.0-124-generic x86_64)  
  
* Documentation:  https://help.ubuntu.com  
* Management:    https://landscape.canonical.com  
* Support:        https://ubuntu.com/pro  
  
System information as of pią, 5 cze 2026, 19:50:39 UTC  
  
System load:  0.0           Temperature:    44.0 C  
Usage of /:   7.3% of 97.87GB Processes:      189  
Memory usage: 5%           Users logged in: 1  
Swap usage:   0%           IPv4 address for eno2: 192.168.10.100  
  
* Strictly confined Kubernetes makes edge and IoT secure. Learn how MicroK8s  
  just raised the bar for easy, resilient and secure K8s cluster deployment.  
  
  https://ubuntu.com/engage/secure-kubernetes-at-the-edge  
  
Przedłużone utrzymanie bezpieczeństwa (ESM) dla Applications nie jest włączone.  
  
44 aktualizacje można zastosować natychmiast.  
Aby wyświetlić te dodatkowe aktualizacje, należy wprowadzić w terminalu: apt list --upgradable  
  
Włącz ESM Apps, aby otrzymywać dodatkowe, przyszłe aktualizacje zabezpieczeń.  
Zobacz https://ubuntu.com/esm lub uruchom: sudo pro status  
  
Last login: Fri Jun  5 19:43:17 2026 from 192.168.0.250  
gf@gf:~$
```