John Danson

ECET 329 - Project 01

2/14/2025

Psuc de code:

Psuedocode

- 1) I will set up the board using the process defined by the book
- 2) Once initialized, I will define mvLED pin to be GPIO Pin 5
- 3) I then will turn the onboard LED on.
- 4) I will then wait 500ms.
- 5) I will then turn the LED off
- 6) I will then wait 500ms
- 7) I will then repeat by to step 4.

How I programed it:

To program the board I decided to create the binary file and then place it onto the Nucleo board.

This was done by changing project properties to allow for the creation of the binary file.

Mys.

```
/* USER CODE BEGIN Header */
 *******************
 * @file
              : main.c
  @brief
              : Main program body
  @attention
 * Copyright (c) 2025 STMicroelectronics.
  All rights reserved.
 * This software is licensed under terms that can be found in the LICENSE file
  in the root directory of this software component.
 * If no LICENSE file comes with this software, it is provided AS-IS.
 ***********************
 */
    Author: John Danison
    Date: 2/14/2025
    Psuedocode:
    1) I will set up the board using the process defined by the book.
    2) Once initialized, I will define myLED pin to be GPIO Pin 5.
    3) I then will turn the onboard LED on.
    4) I will then wait 500ms.
    5) I will then turn the LED off.
    6) I will then wait 500ms.
    7) I will then repeat by to step 4.
/* USER CODE END Header */
/* Includes -----*/
#include "main.h"
/* Private includes -----*/
/* USER CODE BEGIN Includes */
/* USER CODE END Includes */
/* Private typedef -----*/
/* USER CODE BEGIN PTD */
#define myled GPIO_PIN_5
/* USER CODE END PTD */
/* Private define -----*/
/* USER CODE BEGIN PD */
/* USER CODE END PD */
/* Private macro -----*/
/* USER CODE BEGIN PM */
/* USER CODE END PM */
/* Private variables -----*/
UART_HandleTypeDef huart2;
/* USER CODE BEGIN PV */
/* USER CODE END PV */
/* Private function prototypes -----*/
```

```
void SystemClock_Config(void);
static void MX_GPIO_Init(void);
static void MX_USART2_UART_Init(void);
/* USER CODE BEGIN PFP */
/* USER CODE END PFP */
/* Private user code ------*/
/* USER CODE BEGIN 0 */
/* USER CODE END 0 */
 * @brief The application entry point.
 * @retval int
int main(void)
 /* USER CODE BEGIN 1 */
 /* USER CODE END 1 */
 /* MCU Configuration-----*/
 /* Reset of all peripherals, Initializes the Flash interface and the Systick.
 HAL_Init();
 /* USER CODE BEGIN Init */
 /* USER CODE END Init */
  /* Configure the system clock */
 SystemClock_Config();
 /* USER CODE BEGIN SysInit */
 /* USER CODE END SysInit */
 /* Initialize all configured peripherals */
 MX_GPIO_Init();
 MX_USART2_UART_Init();
 /* USER CODE BEGIN 2 */
 /* USER CODE END 2 */
  /* Infinite loop */
  /* USER CODE BEGIN WHILE */
 while (1)
 {
       // Turn on LED
       HAL_GPIO_WritePin(GPIOA, myled, GPIO_PIN_SET);
       HAL_Delay(500);
       // Turn off LED
       HAL_GPIO_WritePin(GPIOA, myled, GPIO_PIN_RESET);
       HAL_Delay(500);
   /* USER CODE END WHILE */
   /* USER CODE BEGIN 3 */
 /* USER CODE END 3 */
```

```
}
   @brief System Clock Configuration
  * @retval None
void SystemClock_Config(void)
 RCC_OscInitTypeDef RCC_OscInitStruct = {0};
 RCC_ClkInitTypeDef RCC_ClkInitStruct = {0};
  /** Configure the main internal regulator output voltage
  */
 if (HAL_PWREx_ControlVoltageScaling(PWR_REGULATOR_VOLTAGE_SCALE1) != HAL_0K)
  {
   Error_Handler();
  /** Initializes the RCC Oscillators according to the specified parameters
  * in the RCC_OscInitTypeDef structure.
 RCC_OscInitStruct.OscillatorType = RCC_OSCILLATORTYPE_HSI;
 RCC_OscInitStruct.HSIState = RCC_HSI_ON;
 RCC_OscInitStruct.HSICalibrationValue = RCC_HSICALIBRATION_DEFAULT;
 RCC_OscInitStruct.PLL.PLLState = RCC_PLL_ON;
 RCC_OscInitStruct.PLL.PLLSource = RCC_PLLSOURCE_HSI;
 RCC_OscInitStruct.PLL.PLLM = 1;
 RCC_OscInitStruct.PLL.PLLN = 10;
 RCC_OscInitStruct.PLL.PLLP = RCC_PLLP_DIV7;
 RCC_OscInitStruct.PLL.PLLQ = RCC_PLLQ_DIV2;
 RCC_OscInitStruct.PLL.PLLR = RCC_PLLR_DIV2;
 if (HAL_RCC_OscConfig(&RCC_OscInitStruct) != HAL_OK)
  {
   Error_Handler();
  }
  /** Initializes the CPU, AHB and APB buses clocks
 RCC_ClkInitStruct.ClockType = RCC_CLOCKTYPE_HCLK|RCC_CLOCKTYPE_SYSCLK
                              |RCC_CLOCKTYPE_PCLK1|RCC_CLOCKTYPE_PCLK2;
 RCC_ClkInitStruct.SYSCLKSource = RCC_SYSCLKSOURCE_PLLCLK;
 RCC_ClkInitStruct.AHBCLKDivider = RCC_SYSCLK_DIV1;
 RCC_ClkInitStruct.APB1CLKDivider = RCC_HCLK_DIV1;
 RCC_ClkInitStruct.APB2CLKDivider = RCC_HCLK_DIV1;
 if (HAL_RCC_ClockConfig(&RCC_ClkInitStruct, FLASH_LATENCY_4) != HAL_0K)
  {
   Error_Handler();
}
/**
  * @brief USART2 Initialization Function
  * @param None
  * @retval None
static void MX_USART2_UART_Init(void)
  /* USER CODE BEGIN USART2_Init 0 */
  /* USER CODE END USART2_Init 0 */
  /* USER CODE BEGIN USART2_Init 1 */
```

```
/* USER CODE END USART2 Init 1 */
  huart2.Instance = USART2;
  huart2.Init.BaudRate = 115200;
  huart2.Init.WordLength = UART_WORDLENGTH_8B;
  huart2.Init.StopBits = UART_STOPBITS_1;
  huart2.Init.Parity = UART_PARITY_NONE;
  huart2.Init.Mode = UART_MODE_TX_RX;
  huart2.Init.HwFlowCtl = UART_HWCONTROL_NONE;
  huart2.Init.OverSampling = UART_OVERSAMPLING_16;
  huart2.Init.OneBitSampling = UART_ONE_BIT_SAMPLE_DISABLE;
  huart2.AdvancedInit.AdvFeatureInit = UART_ADVFEATURE_NO_INIT;
  if (HAL_UART_Init(&huart2) != HAL_OK)
  {
    Error_Handler();
  /* USER CODE BEGIN USART2_Init 2 */
  /* USER CODE END USART2_Init 2 */
}
  * @brief GPIO Initialization Function
  * @param None
  * @retval None
static void MX_GPIO_Init(void)
  GPIO_InitTypeDef GPIO_InitStruct = {0};
/* USER CODE BEGIN MX_GPIO_Init_1 */
/* USER CODE END MX_GPIO_Init_1 */
  /* GPIO Ports Clock Enable */
   _HAL_RCC_GPIOC_CLK_ENABLE();
   _HAL_RCC_GPIOH_CLK_ENABLE();
   _HAL_RCC_GPIOA_CLK_ENABLE();
   _HAL_RCC_GPIOB_CLK_ENABLE();
  /*Configure GPIO pin Output Level */
  HAL_GPIO_WritePin(GPIOA, GPIO_PIN_5, GPIO_PIN_RESET);
  /*Configure GPIO pin : B1_Pin */
  GPIO_InitStruct.Pin = B1_Pin;
  GPIO_InitStruct.Mode = GPIO_MODE_IT_FALLING;
  GPIO_InitStruct.Pull = GPIO_NOPULL;
  HAL_GPIO_Init(B1_GPIO_Port, &GPIO_InitStruct);
  /*Configure GPIO pin : PA5 */
  GPIO_InitStruct.Pin = GPIO_PIN_5;
  GPIO_InitStruct.Mode = GPIO_MODE_OUTPUT_PP;
  GPIO_InitStruct.Pull = GPIO_NOPULL;
  GPI0_InitStruct.Speed = GPI0_SPEED_FREQ_LOW;
  HAL_GPIO_Init(GPIOA, &GPIO_InitStruct);
/* USER CODE BEGIN MX_GPIO_Init_2 */
/* USER CODE END MX_GPIO_Init_2 */
/* USER CODE BEGIN 4 */
/* USER CODE END 4 */
/**
```

```
* @brief This function is executed in case of error occurrence.
  * @retval None
void Error_Handler(void)
  /* USER CODE BEGIN Error_Handler_Debug */
  /* User can add his own implementation to report the HAL error return state */
  __disable_irq();
  while (1)
  {
  /* USER CODE END Error_Handler_Debug */
#ifdef USE_FULL_ASSERT
  * @brief Reports the name of the source file and the source line number
           where the assert_param error has occurred.
 * @param file: pointer to the source file name
  * @param line: assert_param error line source number
  * @retval None
void assert_failed(uint8_t *file, uint32_t line)
  /* USER CODE BEGIN 6 */
  /* User can add his own implementation to report the file name and line
number,
     ex: printf("Wrong parameters value: file %s on line %d\r\n", file, line) */
  /* USER CODE END 6 */
#endif /* USE_FULL_ASSERT */
```