



AMAZON ROUTE 53

- Route 53 is an AWS DNS service
 - The name route 53 comes from port 53
 - 53 is a standard network port used by the DOMAIN NAME SYSTEM (DNS)
-


STEPS TO CREATE ROUTE 53

Step 1: Purchase a Domain

- Purchase a domain from GoDaddy.
 - Example: xxxxx.in/.com/.org/.co
-

Step 2: Launch an EC2 Instance

- Launch an Amazon Linux EC2 instance.
 - Configure the Security Group:
 - SSH (22)
 - HTTP (80)
 - Install Apache using terminal .
 - Verify the website using the Elastic IP.
- 



The screenshot displays the AWS Management Console's EC2 Instances page. At the top, there's a header for 'Instances (1/2)' with a search bar and buttons for 'Connect', 'Instance state', 'Actions', and 'Launch instances'. Below this is a table of instances. The first instance, 'my-web-server' (ID: i-072f5f7cd4be5c63a), is in a 'Running' state with a 't3.micro' instance type. The second instance is 'Unselect instance: my-web-server' (ID: i-134142de27515a) in a 'Terminated' state. Below the table, the 'Details' tab for the 'my-web-server' instance is selected, showing its summary: Instance ID i-072f5f7cd4be5c63a, Public IPv4 address 54.172.241.121, Private IPv4 address 172.31.19.91, and Public DNS ec2-54-172-241-121.compute-1.amazonaws.com.

Name	Instance ID	Instance state	Instance type	Status check	Availability Zone	Public IPv4 DNS
my-web-server	i-072f5f7cd4be5c63a	Running	t3.micro	3/3 checks passed	us-east-1c	ec2-54-172-241-121.co...
Unselect instance: my-web-server	i-134142de27515a	Terminated	t3.micro	-	us-east-1c	-

i-072f5f7cd4be5c63a (my-web-server)

Instance summary

Instance ID: i-072f5f7cd4be5c63a

Public IPv4 address: 54.172.241.121 | [open address](#)


Private IPv4 addresses: 172.31.19.91

Public DNS: ec2-54-172-241-121.compute-1.amazonaws.com | [open](#)

Instance state: Running

Step 3: Allocate an Elastic IP

- Allocate an Elastic IP.
- Associate it with the EC2 instance.
- Verify the website by opening the Elastic IP in a browser.



The screenshot shows the 'Allocate Elastic IP' wizard in the AWS console. The 'Elastic IP address' is 3.234.190.163. Under 'Resource type', 'Instance' is selected. A warning box states: 'If you associate an Elastic IP address with an instance that already has an Elastic IP address associated, the previously associated Elastic IP address will be disassociated, but the address will still be allocated to your account. Learn more'. Below this, the 'Instance' field contains 'i-072f5f7cd4be5c63a'. The 'Private IP address' field contains '172.31.19.91'. At the bottom, the 'Reassociation' section has a checkbox 'Allow this Elastic IP address to be reassociated' which is currently unchecked.

Elastic IP address: 3.234.190.163

Resource type
Choose the type of resource with which to associate the Elastic IP address.

☒ Instance
☐ Network interface

Instance
i-072f5f7cd4be5c63a

Private IP address
The private IP address with which to associate the Elastic IP address.
172.31.19.91

Reassociation
Specify whether the Elastic IP address can be reassociated with a different resource if it already associated with a resource.
☐ Allow this Elastic IP address to be reassociated

Step 4: Create a Public Hosted Zone

- Open Amazon Route 53.
- Create a Public Hosted Zone.
- Enter your domain name
Ex: (xxxxxx.in/.com/.org/.co)

Create hosted zone [Info](#)

Hosted zone configuration

A hosted zone is a container that holds information about how you want to route traffic for a domain, such as example.com, and its subdomains.

Domain name [Info](#)

This is the name of the domain that you want to route traffic for.

Valid characters: a-z, 0-9, ! " # \$ % & ' () * + , - / : ; < = > ? @ [\] ^ _ ` { | } . ~

Description - optional [Info](#)

This value lets you distinguish hosted zones that have the same name.

The description can have up to 256 characters. 0/256

Type [Info](#)

The type indicates whether you want to route traffic on the internet or in an Amazon VPC.



Public hosted zone

A public hosted zone determines how traffic is routed on the internet.



Private hosted zone

A private hosted zone determines how traffic is routed within an Amazon VPC.

Step 5: Update GoDaddy Nameservers

- Copy the NS (Name Server) records from Route 53.
- Go to GoDaddy → Domain → Nameservers.
- Replace the default nameservers with the AWS Route 53 nameservers.

Hosted zone details

Records (2)

Accelerated recovery

DNSSEC

Records (1/2) Info

Delet...

The following table lists the existing records in jaweriyamahin.in.

Filter records by property or value

Type ▼


Record ... ▼

Type ▼

Routin... ▼

- Create an A Record in the Hosted Zone.
- Leave the Record Name blank (root domain).
- Point it to the Elastic IP.

A series of overlapping, textured blue circles and brushstrokes of varying shades, creating an abstract background element at the bottom of the slide.



Step 7: you can verify DNS resolution

➤ Window command prompt

nslookup your domain.com

```
C:\Users\Mahin> nslookup jaweriyamahin.in 8.8.8.8
Server:  dns.google
Address:  8.8.8.8
```

```
Non-authoritative answer:
Name:     jaweriyamahin.in
Address:  3.234.190.163
```


```
C:\Users\Mahin>|
```



Step 8y: Test the Website

- Wait for DNS propagation.
- Open:

<http://yourdomain.com>



Welcome to AWS Cloud

Domain Successfully Configured with Route 53