



Assignment 7: Hosting a website on EC2.


Step 1: Search ec2 and click on Instances appearing under Top features of EC2 service.



Step 2: Click on Launch Instances button.



Step 3: Give a name for the instance and scroll down.



Step 4: Select Ubuntu as the AMI.

aws [Search] [Alt+S] Asia Pacific (Mumbai) Jbhawal (0528-0860-2954) Jbhawal

EC2 > Instances > Launch an instance

Quick Start

Amazon Linux macOS **Ubuntu** Windows Red Hat SUSE Linux Debian

Amazon Machine Image (AMI)

Ubuntu Server 24.04 LTS (HVM), 55D Volume Type
ami-019715e0d74f695be (64-bit (x86)) / ami-0848881f2a3dceb1 (64-bit (Arm))
Virtualization: hvm ENA enabled: true Root device type: ebs

Description

Ubuntu Server 24.04 LTS (HVM), EBS General Purpose (SSD) Volume Type. Support available from Canonical (<http://www.ubuntu.com/cloud/services>).

Canonical, Ubuntu, 24.04, amd64 noble image

Architecture: 64-bit (x86) AMI ID: ami-019715e0d74f695be Publish Date: 2025-12-12 Username: ubuntu Verified provider

Summary

Number of instances: 1

Software Image (AMI): Canonical, Ubuntu, 24.04, amd64...read more

Virtual server type (instance type): t3.micro

Firewall (security group): New security group

Storage (volumes): 1 volume(s) - 8 GiB

Cancel Launch instance Preview code

Step 5: We need to give a key pair. Click on Create new key pair to create a new one.

aws [Search] [Alt+S] Asia Pacific (Mumbai) Jbhawal (0528-0860-2954) Jbhawal

EC2 > Instances > Launch an instance

Key pair (login)

You can use a key pair to securely connect to your instance. Ensure that you have access to the selected key pair before you launch the instance.

Key pair name - required: Select Create new key pair

Network settings

Network: vpc-0bd6e20222ae5c72

Subnet: No preference (Default subnet in any availability zone)

Auto-assign public IP: Enable

Firewall (security groups): Create security group Select existing security group

We'll create a new security group called 'launch-wizard-1' with the following rules:

Cancel Launch instance Preview code

Step 6: Give a key pair name, choose RSA as the key pair type and .pem as the key file format. Click on Create key pair button.

aws [Search] [Alt+S] Asia Pacific (Mumbai) Jbhawal (0528-0860-2954) Jbhawal

EC2 > Instances > Launch an instance

Create key pair

Key pair name: keyPairJb.prac.1

Key pair type: RSA RSA encrypted private and public key pair

Private key file format: .pem For use with OpenSSH

When prompted, store the private key in a secure and accessible location on your computer. You will need it later to connect to your instance. Learn more

Cancel Create key pair

Step 7: Under network settings block, check all the security rules and then click on Launch button.

Step 7: Under network settings block, check all the security rules and then click on Launch button.


Step 8: The green banner denotes successful launch of instance. Click on the instance id to open it.

Step 8: The green banner denotes successful launch of instance. Click on the instance id to open it.


Step 9: Copy the public IPv4 address.

Step 9: Copy the public IPv4 address.


Step 10: In Bitvise SSH Client software, enter the copied IPv4 address in the Host server address. Click on Client key manager to add desired Client key.




Step 11: Import the previously created key pair and select it as the Client key.



Step 12: On host key verification popup, click Accept and Save.




Step 13: Click on New Terminal Console.




Step 14: Fetch all latest version of packages and update, upgrade them by writing the following commands:

`sudo apt-get update`


`sudo apt-get upgrade`. Write Y if asked.



Step 15: Write sudo apt-get install nginx. Write Y if asked.




Step 16: After nginx was successful installed, go to Bitvise SFTP. In the local files section, go to the folder where the files needed to be shared to published are present.



Step 17: Go back to the terminal. To give access for sharing of public files to the remote server, we need to give permission to www folder. To do so go to the path /var/www and write the command: `sudo chmod 777 html`

```
ubuntu@13.126.67.158:22 - Bitvise xterm - ubuntu@ip-172-31-42-125: /var/www
Scanning candidates...
Scanning linux images...
Running kernel seems to be up-to-date.
Restarting services...
Service restarts being deferred:
/etc/needrestart/restart.d/dbus.service
systemctl restart getty@tty1.service
systemctl restart networkd-dispatcher.service
systemctl restart serial-getty@ttyS0.service
systemctl restart systemd-logind.service
systemctl restart unattended-upgrades.service
No containers need to be restarted.
User sessions running outdated binaries:
ubuntu @ session #2: sshd[1052,1164]
ubuntu @ user manager service: systemd[1058]
No VM guests are running outdated hypervisor (qemu) binaries on this host.
ubuntu@ip-172-31-42-125:~$ nginx -v
nginx version: nginx/1.24.0 (Ubuntu)
ubuntu@ip-172-31-42-125:~$ pwd
/home/ubuntu
ubuntu@ip-172-31-42-125:~$ cd ../../
ubuntu@ip-172-31-42-125:/$ pwd
/
ubuntu@ip-172-31-42-125:/$ cd /var/www/html
ubuntu@ip-172-31-42-125:/var/www/html$ ls
index.nginx-debian.html
ubuntu@ip-172-31-42-125:/var/www/html$ cd ..
ubuntu@ip-172-31-42-125:/var/www$ sudo chmod 777 html
ubuntu@ip-172-31-42-125:/var/www$
```

Step 18: Go back to Bitvise. Go to the path /var/www/html in Remote files section. Drag and drop the local files into the live server which are needed to be hosted. Make sure there is one index.html file as it is going to be the starting point of the webpage we are hosting.



Step 19: In the browser, paste the public IPv4 address previously copied. We can see our webpage successfully hosted.



This is main page

[Previous page](#) [Next page](#)