CN Assignment-10

Jeetu Mehra

U24AI032

1) Configure the network below using two routers, one wireless and another 1841 router.



Connect PC's wirelessly

Go to physical→click red button→Replace with WMP300N→click reb button→repeat for other PCs and Laptops


PC5
Physical
Config
Desktop
Programming
Attributes
MODULES
WMP300N
PT-HOST-NM-1AM
PT-HOST-NM-1CE
PT-HOST-NM-1CFE
PT-HOST-NM-1CGE
PT-HOST-NM-1FFE
PT-HOST-NM-1FGE
PT-HOST-NM-1W
PT-HOST-NM-1W-A
PT-HOST-NM-1W-AC
PT-HOST-NM-3G/4G
PT-HOST-NM-COVER
PT-HEADPHONE
PT-MICROPHONE
Zoom


1841
Router0
WRT300N
Wireless Router0
Switch0
Laptop-PT
Laptop0
PC-PT
PC0
PC-PT
PC1
PC-PT
PC2
PC-PT
PC3
PC-PT
PC4
PC-PT
PC5
PC-PT
PC6
PC-PT
PC7
PC-PT
PC8
TabletPC-PT
Tablet PC0
TabletPC-PT
Tablet PC1
TabletPC-PT
Tablet PC2
TabletPC-PT
Tablet PC3
Laptop-PT
Laptop4
Laptop-PT
Laptop1
Laptop-PT
Laptop2
Laptop-PT
Laptop3


TabletPC-PT
Tablet PC0
TabletPC-PT
Tablet PC1
TabletPC-PT
Tablet PC2
TabletPC-PT
Tablet PC3
1841
Router0
WRT300N
Wireless Router0
Laptop-PT
Laptop4
Laptop-PT
Laptop1
Laptop-PT
Laptop2
Laptop-PT
Laptop3
2950-24TT
Switch0
Laptop-PT
Laptop0
PC-PT
PC0
PC-PT
PC1
PC-PT
PC2
PC-PT
PC3
PC-PT
PC4
PC-PT
PC5
PC-PT
PC6
PC-PT
PC7
PC-PT
PC8


PC0
Physical
Config
Desktop
Programming
Attributes
IP Configuration
Interface
FastEthernet0
IP Configuration
DHCP
Static
IPv4 Address
192.168.1.2
Subnet Mask
255.255.255.0
Default Gateway
192.168.1.1
DNS Server
0.0.0.0
IPv6 Configuration


PC1
Physical
Config
Desktop
Programming
Attributes
IP Configuration
Interface
FastEthernet0
IP Configuration
DHCP
Static
IPv4 Address
192.168.1.3
Subnet Mask
255.255.255.0
Default Gateway
192.168.1.1
DNS Server
0.0.0.0


PC2
Physical
Config
Desktop
Programming
Attributes
IP Configuration
Interface
FastEthernet0
IP Configuration
DHCP
Static
IPv4 Address
192.168.1.4
Subnet Mask
255.255.255.0
Default Gateway
192.168.1.1
DNS Server
0.0.0.0


PC3
Physical
Config
Desktop
Programming
Attributes
IP Configuration
Interface
FastEthernet0
IP Configuration
DHCP
Static
IPv4 Address
192.168.1.5
Subnet Mask
255.255.255.0
Default Gateway
192.168.1.1
DNS Server
0.0.0.0


PC4
Physical
Config
Desktop
Programming
Attributes
IP Configuration
Interface
FastEthernet0
IP Configuration
DHCP
Static
IPv4 Address
192.168.1.6
Subnet Mask
255.255.255.0
Default Gateway
192.168.1.1
DNS Server
0.0.0.0


Laptop0
Physical
Config
Desktop
Programming
Attributes
IP Configuration
Interface
FastEthernet0
IP Configuration
DHCP
Static
IPv4 Address
192.168.1.7
Subnet Mask
255.255.255.0
Default Gateway
192.168.1.1
DNS Server
0.0.0.0


Router0
Physical
Config
CLI
Attributes
GLOBAL
Settings
Algorithm Settings
ROUTING
Static
RIP
SWITCHING
VLAN Database
INTERFACE
FastEthernet0/0
FastEthernet0/1
FastEthernet0/0
Port Status
On
Bandwidth
100 Mbps
10 Mbps
Auto
Duplex
Half Duplex
Full Duplex
Auto
MAC Address
0001.C7DA.2601
IP Configuration
IPv4 Address
192.168.1.1
Subnet Mask
255.255.255.0
Tx Ring Limit
10


Router0
Physical
Config
CLI
Attributes
GLOBAL
Settings
Algorithm Settings
ROUTING
Static
RIP
SWITCHING
VLAN Database
INTERFACE
FastEthernet0/0
FastEthernet0/1
FastEthernet0/1
Port Status
On
Bandwidth
100 Mbps
10 Mbps
Auto
Duplex
Half Duplex
Full Duplex
Auto
MAC Address
0001.C7DA.2602
IP Configuration
IPv4 Address
192.168.4.1
Subnet Mask
255.255.255.0
Tx Ring Limit
10


Wireless Router0
Physical
Config
GUI
Attributes
GLOBAL
Settings
Algorithm Settings
INTERFACE
Internet
LAN
Wireless
Internet Settings
IP Configuration
DHCP
Static
PPPoE
UserName
Password
IPv4 Address
Subnet Mask
Default Gateway
192.168.4.1
DNS Server


Wireless Router0
Physical
Config
GUI
Attributes
GLOBAL
Settings
Algorithm Settings
INTERFACE
Internet
LAN
Wireless
LAN Settings
IP Configuration
IPv4 Address
192.168.4.2
Subnet Mask
255.255.255.0


Wireless Router0
Physical
Config
GUI
Attributes
GLOBAL
Settings
Algorithm Settings
INTERFACE
Internet
LAN
Wireless
Wireless Settings
SSID
Arushi
2.4 GHz Channel
6 - 2.437GHz
Coverage Range (meters)
250.00
Authentication
Disabled
WEP
WEP Key
0123456789
WPA-PSK
WPA2-PSK
PSK Pass Phrase
WPA
WPA2
RADIUS Server Settings
IP Address
Shared Secret
Encryption Type
40/64-Bits (10 Hex digits)



Select PC5→go to desktop→go to PC wireless→click refresh→click Arushi→click connect→enter WEP key→ click connect→Repeat for other devices




PC5
Physical
Config
Desktop
Programming
Attributes
Link Information
Connect
Profiles
More Information
Infrastructure Mode
2.4GHz
You have successfully connected to the access point
Signal Strength
Link Quality
Adapter is Active
Wireless-N Notebook Adapter
Wireless Network Monitor v1.0
Model No. WPC300N


TabletPC-PT
Tablet PC0
TabletPC-PT
Tablet PC1
TabletPC-PT
Tablet PC2
TabletPC-PT
Tablet PC3
1841
Router0
WRT300N
Wireless Router0
Laptop-PT
Laptop4
Laptop-PT
Laptop1
Laptop-PT
Laptop2
Laptop-PT
Laptop3
Laptop-PT
Laptop0
PC-PT
PC0
PC-PT
PC1
PC-PT
PC2
PC-PT
PC3
PC-PT
PC4
PC-PT
PC5
PC-PT
PC6
PC-PT
PC7
PC-PT
PC8

For tablet


Tablet PC0
Physical
Config
Desktop
Programming
Attributes
GLOBAL
Settings
Algorithm Settings
INTERFACE
Wireless0
3G/4G Cell1
Bluetooth
Wireless0
Port Status
On
Bandwidth
300 Mbps
MAC Address
0040.0B58.A390
SSID
Arushi
Authentication
Disabled
WEP
WPA-PSK
WPA2-PSK
WPA
WPA2
802.1X
Method:
WEP Key
0123456789
PSK Pass Phrase
User ID
Password
MD5
User Name
Password
Encryption Type
40/64-Bits (10 Hex digits)


TabletPC-PT
Tablet PC0
TabletPC-PT
Tablet PC1
TabletPC-PT
Tablet PC2
TabletPC-PT
Tablet PC3
1841
Router0
WRT300N
Wireless Router0
2950-24TT
Switch0
Laptop-PT
Laptop4
Laptop-PT
Laptop1
Laptop-PT
Laptop2
Laptop-PT
Laptop3
Laptop-PT
Laptop0
PC-PT
PC0
PC-PT
PC1
PC-PT
PC2
PC-PT
PC3
PC-PT
PC4
PC-PT
PC5
PC-PT
PC6
PC-PT
PC7
PC-PT
PC8



IP PC6=192.168.4.3

IP PC7=192.168.4.4

IP PC8=192.168.4.5

IP Laptop1=192.168.4.6

IP Laptop2=192.168.4.7

IP Laptop3=192.168.4.8

IP Laptop4=192.168.4.9

IP Tablet0=192.168.4.10

IP Tablet1=192.168.4.11

IP Tablet2=192.168.4.12

IP Tablet3=192.168.4.13

PC0

Physical Config Desktop Programming Attributes

Command Prompt

```
Cisco Packet Tracer PC Command Line 1.0
C:\>ping 192.168.4.2

Pinging 192.168.4.2 with 32 bytes of data:

Request timed out.
Reply from 192.168.4.2: bytes=32 time<1ms TTL=254
Reply from 192.168.4.2: bytes=32 time<1ms TTL=254
Reply from 192.168.4.2: bytes=32 time<1ms TTL=254

Ping statistics for 192.168.4.2:
    Packets: Sent = 4, Received = 3, Lost = 1 (25% loss),
Approximate round trip times in milli-seconds:
    Minimum = 0ms, Maximum = 0ms, Average = 0ms

C:\>ping 192.168.4.2

Pinging 192.168.4.2 with 32 bytes of data:

Reply from 192.168.4.2: bytes=32 time<1ms TTL=254
Reply from 192.168.4.2: bytes=32 time<1ms TTL=254
Reply from 192.168.4.2: bytes=32 time=17ms TTL=254
Reply from 192.168.4.2: bytes=32 time=1ms TTL=254

Ping statistics for 192.168.4.2:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
Approximate round trip times in milli-seconds:
    Minimum = 0ms, Maximum = 17ms, Average = 4ms

C:\>ping 192.168.4.9

Pinging 192.168.4.9 with 32 bytes of data:

Request timed out.
Reply from 192.168.4.9: bytes=32 time=22ms TTL=127
Reply from 192.168.4.9: bytes=32 time=31ms TTL=127
Reply from 192.168.4.9: bytes=32 time=37ms TTL=127

Ping statistics for 192.168.4.9:
    Packets: Sent = 4, Received = 3, Lost = 1 (25% loss),
Approximate round trip times in milli-seconds:
    Minimum = 22ms, Maximum = 37ms, Average = 30ms
```

PC0

Physical Config Desktop Programming Attributes

Command Prompt

```
Approximate round trip times in milli-seconds:
    Minimum = 22ms, Maximum = 37ms, Average = 30ms

C:\>ping 192.168.4.9

Pinging 192.168.4.9 with 32 bytes of data:

Reply from 192.168.4.9: bytes=32 time=36ms TTL=127
Reply from 192.168.4.9: bytes=32 time=44ms TTL=127
Reply from 192.168.4.9: bytes=32 time=25ms TTL=127
Reply from 192.168.4.9: bytes=32 time=18ms TTL=127

Ping statistics for 192.168.4.9:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
Approximate round trip times in milli-seconds:
    Minimum = 18ms, Maximum = 44ms, Average = 30ms

C:\>ping 192.168.4.13

Pinging 192.168.4.13 with 32 bytes of data:

Request timed out.
Reply from 192.168.4.13: bytes=32 time=30ms TTL=127
Reply from 192.168.4.13: bytes=32 time=10ms TTL=127
Reply from 192.168.4.13: bytes=32 time=32ms TTL=127

Ping statistics for 192.168.4.13:
    Packets: Sent = 4, Received = 3, Lost = 1 (25% loss),
Approximate round trip times in milli-seconds:
    Minimum = 10ms, Maximum = 32ms, Average = 24ms

C:\>ping 192.168.4.13

Pinging 192.168.4.13 with 32 bytes of data:

Reply from 192.168.4.13: bytes=32 time=29ms TTL=127
Reply from 192.168.4.13: bytes=32 time=16ms TTL=127
Reply from 192.168.4.13: bytes=32 time=22ms TTL=127
Reply from 192.168.4.13: bytes=32 time=21ms TTL=127

Ping statistics for 192.168.4.13:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
Approximate round trip times in milli-seconds:
    Minimum = 16ms, Maximum = 29ms, Average = 22ms
```



2) Configure the FTP server as shown in the below network.




Router1
Physical
Config
CLI
Attributes
GLOBAL
Settings
Algorithm Settings
ROUTING
Static
RIP
SWITCHING
VLAN Database
INTERFACE
FastEthernet0/0
FastEthernet0/1
FastEthernet0/1
Port Status
On
Bandwidth
100 Mbps
10 Mbps
Auto
Duplex
Half Duplex
Full Duplex
Auto
MAC Address
00E0.F7D1.4402
IP Configuration
IPv4 Address
192.168.0.1
Subnet Mask
255.255.255.0
Tx Ring Limit
10


PC9
Physical
Config
Desktop
Programming
Attributes
IP Configuration
X
Interface
FastEthernet0
IP Configuration
DHCP
Static
IPv4 Address
192.168.0.2
Subnet Mask
255.255.255.0
Default Gateway
192.168.0.1
DNS Server
0.0.0.0


PC10
Physical
Config
Desktop
Programming
Attributes
IP Configuration
X
Interface
FastEthernet0
IP Configuration
DHCP
Static
IPv4 Address
192.168.0.3
Subnet Mask
255.255.255.0
Default Gateway
192.168.0.1
DNS Server
0.0.0.0







Go to text editor in PC9


PC9
Physical
Config
Desktop
Programming
Attributes
Text Editor
File
Hello World!!

PC9

Physical | Config | Desktop | Programming | Attributes

Command Prompt

```
Cisco Packet Tracer PC Command Line 1.0
C:\>ping 10.10.10.1

Pinging 10.10.10.1 with 32 bytes of data:

Reply from 10.10.10.1: bytes=32 time<1ms TTL=255
Reply from 10.10.10.1: bytes=32 time<1ms TTL=255
Reply from 10.10.10.1: bytes=32 time<1ms TTL=255
Reply from 10.10.10.1: bytes=32 time<1ms TTL=255

Ping statistics for 10.10.10.1:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
Approximate round trip times in milli-seconds:
    Minimum = 0ms, Maximum = 0ms, Average = 0ms

C:\>ping 10.10.10.2

Pinging 10.10.10.2 with 32 bytes of data:

Request timed out.
Reply from 10.10.10.2: bytes=32 time<1ms TTL=127
Reply from 10.10.10.2: bytes=32 time<1ms TTL=127
Reply from 10.10.10.2: bytes=32 time=1ms TTL=127

Ping statistics for 10.10.10.2:
    Packets: Sent = 4, Received = 3, Lost = 1 (25% loss),
Approximate round trip times in milli-seconds:
    Minimum = 0ms, Maximum = 1ms, Average = 0ms

C:\>ping 10.10.10.2

Pinging 10.10.10.2 with 32 bytes of data:

Reply from 10.10.10.2: bytes=32 time<1ms TTL=127
Reply from 10.10.10.2: bytes=32 time<1ms TTL=127
Reply from 10.10.10.2: bytes=32 time<1ms TTL=127
Reply from 10.10.10.2: bytes=32 time<1ms TTL=127

Ping statistics for 10.10.10.2:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
Approximate round trip times in milli-seconds:
    Minimum = 0ms, Maximum = 0ms, Average = 0ms
```

PC9

Physical Config Desktop Programming Attributes

Command Prompt

```
C:\>ftp
Cisco Packet Tracer PC Ftp

Usage: ftp target

C:\>ftp 10.10.10.2
Trying to connect...10.10.10.2
Connected to 10.10.10.2
220- Welcome to PT Ftp server
Username:Arushi
331- Username ok, need password
Password:
230- Logged in
(passive mode On)
ftp>put hello.txt

Writing file hello.txt to 10.10.10.2:
File transfer in progress...

[Transfer complete - 13 bytes]

13 bytes copied in 0.041 secs (317 bytes/sec)
```

```
ftp>dir

Listing /ftp directory from 10.10.10.2:
0   : asa842-k8.bin                                    5571584
1   : asa923-k8.bin                                    30468096
2   : c1841-advipservicesk9-mz.124-15.T1.bin           33591768
3   : c1841-ipbase-mz.123-14.T7.bin                    13832032
4   : c1841-ipbasek9-mz.124-12.bin                     16599160
5   : c1900-universalk9-mz.SPA.155-3.M4a.bin           33591768
6   : c2600-advipservicesk9-mz.124-15.T1.bin           33591768
7   : c2600-i-mz.122-28.bin                            5571584
8   : c2600-ipbasek9-mz.124-8.bin                      13169700
9   : c2800nm-advipservicesk9-mz.124-15.T1.bin         50938004
10  : c2800nm-advipservicesk9-mz.151-4.M4.bin          33591768
11  : c2800nm-ipbase-mz.123-14.T7.bin                  5571584
12  : c2800nm-ipbasek9-mz.124-8.bin                    15522644
13  : c2900-universalk9-mz.SPA.155-3.M4a.bin           33591768
14  : c2950-i6q412-mz.121-22.EA4.bin                   3058048
15  : c2950-i6q412-mz.121-22.EA8.bin                   3117390
16  : c2960-lanbase-mz.122-25.FX.bin                   4414921
17  : c2960-lanbase-mz.122-25.SEE1.bin                 4670455
18  : c2960-lanbasek9-mz.150-2.SE4.bin                 4670455
19  : c3560-advipservicesk9-mz.122-37.SE1.bin          8662192
20  : c3560-advipservicesk9-mz.122-46.SE.bin           10713279
21  : c800-universalk9-mz.SPA.152-4.M4.bin             33591768
22  : c800-universalk9-mz.SPA.154-3.M6a.bin            83029236
23  : cat3k_caa-universalk9.16.03.02.SPA.bin           505532849
24  : cgr1000-universalk9-mz.SPA.154-2.CG              159487552
25  : cgr1000-universalk9-mz.SPA.156-3.CG              184530138
26  : hello.txt                                        13
27  : ir800-universalk9-bundle.SPA.156-3.M.bin         160968869
28  : ir800-universalk9-mz.SPA.155-3.M                 61750062
29  : ir800-universalk9-mz.SPA.156-3.M                 63753767
30  : ir800_yocto-1.7.2.tar                            2877440
31  : ir800_yocto-1.7.2_python-2.7.3.tar               6912000
32  : pt1000-i-mz.122-28.bin                           5571584
33  : pt3000-i6q412-mz.121-22.EA4.bin                  3117390
ftp>
```

PC10

Physical Config Desktop Programming Attributes

Command Prompt

```
Cisco Packet Tracer PC Command Line 1.0
C:\>ftp 10.10.10.2
Trying to connect...10.10.10.2
Connected to 10.10.10.2
220- Welcome to PT Ftp server
Username:Arushi
331- Username ok, need password
Password:
230- Logged in
(passive mode On)
ftp>put hello.txt
%Error opening c:hello.txt (No such file or directory)
ftp>get hello.txt

Reading file hello.txt from 10.10.10.2:
File transfer in progress...

[Transfer complete - 13 bytes]

13 bytes copied in 0.01 secs (1300 bytes/sec)
ftp>dir
```

```
Listing /ftp directory from 10.10.10.2:
0   : asa842-k8.bin                                        5571584
1   : asa923-k8.bin                                        30468096
2   : c1841-advipservicesk9-mz.124-15.T1.bin               33591768
3   : c1841-ipbase-mz.123-14.T7.bin                        13832032
4   : c1841-ipbasek9-mz.124-12.bin                         16599160
5   : c1900-universalk9-mz.SPA.155-3.M4a.bin               33591768
6   : c2600-advipservicesk9-mz.124-15.T1.bin               33591768
7   : c2600-i-mz.122-28.bin                                5571584
8   : c2600-ipbasek9-mz.124-8.bin                          13169700
9   : c2800nm-advipservicesk9-mz.124-15.T1.bin             50938004
10  : c2800nm-advipservicesk9-mz.151-4.M4.bin              33591768
11  : c2800nm-ipbase-mz.123-14.T7.bin                      5571584
12  : c2800nm-ipbasek9-mz.124-8.bin                        15522644
13  : c2900-universalk9-mz.SPA.155-3.M4a.bin               33591768
14  : c2950-i6q412-mz.121-22.EA4.bin                       3058048
15  : c2950-i6q412-mz.121-22.EA8.bin                       3117390
16  : c2960-lanbase-mz.122-25.FX.bin                       4414921
17  : c2960-lanbase-mz.122-25.SEE1.bin                     4670455
18  : c2960-lanbasek9-mz.150-2.SE4.bin                     4670455
19  : c3560-advipservicesk9-mz.122-37.SE1.bin              8662192
20  : c3560-advipservicesk9-mz.122-46.SE.bin               10713279
21  : c800-universalk9-mz.SPA.152-4.M4.bin                 33591768
22  : c800-universalk9-mz.SPA.154-3.M6a.bin                83029236
23  : cat3k_caa-universalk9.16.03.02.SPA.bin               505532849
24  : cgr1000-universalk9-mz.SPA.154-2.CG                  159487552
25  : cgr1000-universalk9-mz.SPA.156-3.CG                  184530138
26  : hello.txt                                            13
27  : ir800-universalk9-bundle.SPA.156-3.M.bin             160968869
28  : ir800-universalk9-mz.SPA.155-3.M                     61750062
29  : ir800-universalk9-mz.SPA.156-3.M                     63753767
30  : ir800_yocto-1.7.2.tar                                2877440
31  : ir800_yocto-1.7.2_python-2.7.3.tar                   6912000
32  : pt1000-i-mz.122-28.bin                               5571584
33  : pt3000-i6q412-mz.121-22.EA4.bin                      3117390
ftp>
```



3) Configure the email server as shown in the network below.




Router2
Physical
Config
CLI
Attributes
GLOBAL
Settings
Algorithm Settings
ROUTING
Static
RIP
SWITCHING
VLAN Database
INTERFACE
FastEthernet0/0
FastEthernet0/1
FastEthernet0/1
Port Status
On
Bandwidth
100 Mbps
10 Mbps
Auto
Duplex
Half Duplex
Full Duplex
Auto
MAC Address
0050.0F11.6202
IP Configuration
IPv4 Address
192.168.1.1
Subnet Mask
255.255.255.0
Tx Ring Limit
10


PC11
Physical
Config
Desktop
Programming
Attributes
IP Configuration
X
Interface
FastEthernet0
IP Configuration
DHCP
Static
IPv4 Address
10.0.0.2
Subnet Mask
255.0.0.0
Default Gateway
10.0.0.1
DNS Server
0.0.0.0


PC12
Physical
Config
Desktop
Programming
Attributes
IP Configuration
X
Interface
FastEthernet0
IP Configuration
DHCP
Static
IPv4 Address
10.0.0.3
Subnet Mask
255.0.0.0
Default Gateway
10.0.0.1
DNS Server
0.0.0.0


Server1
Physical
Config
Services
Desktop
Programming
Attributes
IP Configuration
X
IP Configuration
DHCP
Static
IPv4 Address
192.168.1.2
Subnet Mask
255.255.255.0
Default Gateway
192.168.1.1
DNS Server
0.0.0.0


Server1
Physical
Config
Services
Desktop
Programming
Attributes
SERVICES
HTTP
DHCP
DHCPv6
TFTP
DNS
SYSLOG
AAA
NTP
EMAIL
FTP
IoT
VM Management
Radius EAP
EMAIL
SMTP Service
ON
OFF
POP3 Service
ON
OFF
Domain Name:
gmail.com
Set
User Setup
User
Arushi2
Password
123
Arushi
+


Server1
Physical
Config
Services
Desktop
Programming
Attributes
SERVICES
HTTP
DHCP
DHCPv6
TFTP
DNS
SYSLOG
AAA
NTP
EMAIL
FTP
IoT
VM Management
Radius EAP
EMAIL
SMTP Service
ON
OFF
POP3 Service
ON
OFF
Domain Name:
gmail.com
Set
User Setup
User
Password
Arushi
Arushi2



Click Save



Click Save

Go to PC11→Desktop→Email→Compose



Go to PC12→click receive→click reply






PC11
Physical
Config
Desktop
Programming
Attributes
MAIL BROWSER
X
Mails
Compose
Reply
Receive
Delete
Configure Mail
From
Subject
Received
1
Arushi2@gmail.com
RE: test mail
Sun Apr 19 2026 01:43:41
RE: test mail
Arushi2@gmail.com
Sent : Sun Apr 19 2026 01:43:41
hiii
Subject : test mail
From : Arushi@gmail.com
Sent : Sun Apr 19 202601:41:30
hello