UNIVERSITY OF CAMBRIDGE

Department of Computer Science and Technology

Computer Laboratory > Projects and initiatives > Raspberry Pi > Tutorials > Raspberry Pi Turing Machines > Introduction: What is a Turing machine?

Raspberry Pi Quick Start Raspberry Pi Temperature Sensor Science Experiments with RPii Baking Pi – Operating Systems

Development »

hardware.

Raspberry Pi

Raspberry Pi Turing Machines

Introduction: What is a Turing machine?

Section 4: Turing Machine Example

Section 2: GPIO Section 3: Turing machine

Programs **Distributed Computing with the**

Raspberry Pi Image Pi – Basic image processing Home - Physical Computing with

Raspberry Pi

Contents What is a Turing machine? A simple demonstration A simple program The machine state Finite state machines

What is a Turing machine?

A Turing machine is a hypothetical machine thought of by the mathematician Alan Turing in 1936. Despite its simplicity, the machine can simulate ANY computer algorithm, no matter how complicated it is!

other form of data storage. The squares on the tape are usually blank at the start and can be written with symbols. In this case, the machine can only process the symbols 0 and 1 and " " (blank), and is thus said to be a 3-symbol Turing machine.

Above is a very simple representation of a Turing machine. It consists of an infinitely-long tape which acts like the memory in a typical computer, or any

At any one time, the machine has a head which is positioned over one of the squares on the tape. With this head, the machine can perform three very basic operations:

1. Read the symbol on the square under the head. 2. Edit the symbol by writing a new symbol or erasing it.

3. Move the tape left of right by one square so that the machine can read and edit the symbol on a neighbouring square.

A simple demonstration

As a trivial example to demonstrate these operations, let's try printing the symbols "1 1 0" on an initially blank tape: First, we write a 1 on the square under the head: Next, we move the tape left by one square: Now, write a 1 on the new square under the head: We then move the tape left by one square again: Finally, write a 0 and that's it!

A simple program


With the symbols "1 1 0" printed on the tape, let's attempt to convert the 1s to 0s and vice versa. This is called bit inversion, since 1s and 0s are bits in binary. This can be done by passing the following instructions to the Turing machine, utilising the machine's reading capabilities to decide its subsequent operations on its own. These instructions make up a simple program.

Symbol read Write instruction Move instruction

Blank None None Write 1 Move tape to the right Move tape to the right Write 0

The machine will first read the symbol under the head, write a new symbol accordingly, then move the tape left or right as instructed, before repeating the read-write-move sequence again.

Let's see what this program does to our tape from the previous end point of the instructions:



Finally, a 'blank' symbol is read, so the machine does nothing apart from read the blank symbol continuously since we have instructed it to repeat the read-write-move sequence without stopping.

In fact, the program is incomplete. How does the machine repeat the sequence endlessly, and how does the machine stop running the program? The program tells it to with the concept of a **machine state**.

The machine state

To complete the program, the state changes during the execution of the program on the machine must be considered. The following changes, marked in *italics*, must be aded to our table which can now be called a **state table**: **State** Symbol read Write instruction Move instruction Next state

	State 0	Blank	None	None	Stop state	
		0	Write 1	Move the tape to the right	State 0	
		1	Write 0	Move the tape to the right	State 0	
We allocate the previous set of instructions to a machine state, so that the machine w						

will perform those instructions when it is in the specified state. After every instruction, we also specify a state for the machine to transition to. In the example, the machine is redirected back to its original state,

State 0, to repeat the read-write-nove sequence, unless a blank symbol is read. When the machine reads a blank symbol, the machine is directed to a stop state and the program terminates.

Finite state machines Even though it seems silly to do so, let's now add an additional state to our program that reverts the already inverted bits "1 1 0" back from "0 0 1" to


"1 1 0". Below is the updated table, with changes listed in *italics*. The Turing machine now acts like a finite state machine with two states—these are called three-symbol, two-state Turing machines.

Next state

State 0	Blank	Write blank	Move the tape to the left	State 1			
	0	Write 1	Move the tape to the right	State 1			
	1	Write 0	Move the tape to the right	State 0			
State 1	Blank	Write blank	Move the tape to the right	Stop state			
	0	Write 1	Move the tape to the left	State 1			
	1	Write 0	Move the tape to the left	State 1			
For the write instruction, "None" has been changed to "Write blank" for uniformity's sake (so that only the machine's symbols are referred to), and it should be noted that they are equivalent.							


State Symbol read Write instruction Move instruction

Instead of a state table, the program can also be represented with a state diagram:



Instruction when 'Blank' symbol is read Instruction when '0' symbol is read

Instruction when '1' symbol is read From where the program was previously, instead of doing nothing and stopping after the machine encounters a blank symbol, we instruct it to move the tape left before transitioning to State 1 where it reverses the bit inversion process.



Finally, a blank symbol is read, so we move the tape right to get back to where we started, and stop the program.

With the introduction of more states to our program, we can instruct the Turing machine to perform more complex functions and hence run any

algorithm that a modern day computer can. In section two, let's learn about LEDs, GPIO pins, resistors, and python, before embarking on building our Turing machine!