

Database alignment preset

Nested constellation and block levels with scoped routing pipes

LEVEL 1

Locations

Three internal block levels exercise nested alignment and routing.

BLOCK LEVEL 1

types_locations		
Name	Type	Attrs
type_id	int	NN PK
name	var 255	NN

regions		
Name	Type	Attrs
region_id	int	PK NN
name	var 120	NN UN

BLOCK LEVEL 2

locations		
Name	Type	Attrs
location_id	int	PK NN
name	var 255	NN UN
country	var 255	
region	var 255	
city	var 255	
latitude	float	
longitude	float	
type_id	int	NN FK
active	bool	NN Dtrue

location_aliases		
Name	Type	Attrs
alias_id	int	PK NN
location_id	int	FK NN
alias	var 120	NN

BLOCK LEVEL 3

location_events		
Name	Type	Attrs
event_id	int	PK NN
location_id	int	FK NN
type_id	int	FK NN
parent_event_id	int	FK
occurred_at	tstz	NN

L1 / O1

Maintenance

A child constellation with an outer direct reference to Locations.

BLOCK LEVEL 1

mc_site_types		
Name	Type	Attrs
type_id	int	PK NN
name	var 120	NN UN

BLOCK LEVEL 2

mc_sites		
Name	Type	Attrs
site_id	int	PK NN
location_id	int	FK NN
type_id	int	FK NN
name	var 120	NN

L2 / O1

Author

Javier Soler

Sensomatic SAS

Version	0.1.0
Date	2026-07-15

Legend

Constraints

PK	Primary key
FK	Foreign key
NN	Not nullable
UN	Unique constraint
Dnow	Default value is now

Data types

int	Integer number
var n	Variable character text with maximum length n
tstz	Timestamp with time zone

Direct arrows

Cross-constellation links use outer pipes;
adjacent internal block levels use constellation-
scoped inner pipes.

```
lo_locations_type_fk
internal / adjacent-level auto -> direct
locations.type_id -> types_locations.type_id
```

```
lo_events_location_fk
internal / adjacent-level auto -> direct
location_events.location_id ->
locations.location id
```

```
mc_sites_type_fk
internal / adjacent-level auto -> direct
mc_sites.type_id -> mc_site_types.type_id
```

```
mc_sites_location_fk
cross-constellation / adjacent-level auto -> direct
mc_sites.location_id -> locations.location_id
```

Link-blocks

Rows show compact badges with local arrows. Source badges jump to their target row when that row is on the current page.

```
lo_aliases_location_fk
internal / same-level auto -> link-block
location_aliases.location_id ->
locations.location_id
```

```
lo_events_type_fk
internal / skip-level auto -> link-block
location_events.type_id ->
types_locations.type_id
```

```
lo_events_parent_fk
same-block / same-block auto -> link-block
location_events.parent_event_id
location_events.event_id
```

Comments

Blocks use manual levels and orders inside each constellation. Adjacent internal references use inner pipes; cross-constellation references keep the outer pipes.