Topology



All IP Addressing

Palo Alto	Eth 1 / 1: 192.12.206.133	Eth 1 / 2: 192.168.20.1	Transit: 10.0.0.1 255.255.255.252	Management: 192.168.20.3
Proxmox Linux Server	192.168.20.4			
Linux 1	192.168.20.5			
Linux 2	192.168.20.6			
Linux 3	192.168.20.7			
Linux 4	192.168.20.8			
Ubutnu Ecom	192.168.20.9			
Fedora Webmail	192.168.20.10			
Oracle Splunk	192.168.20.11			
Ubuntu Wkst	192.168.20.12			
Spare Address	192.168.20.13 To 192.68.20.254			
Cisco Firewall	Eth 1 / 1: 192.12.206.134	Eth 1 / 2: 192.168.40.1	Transit: 10.0.0.2 255.255.255.252	Management: 192.168.40.3
Proxmox Windows Server	192.168.40.4			
Win 1	192.168.40.5			
Win 2	192.168.40.6			
Win 3	192.168.40.7			
Win 4	192.168.40.8			
AD/DNS	192.168.40.9			
Web Server	192.168.40.10			
FTP Server	192.168.40.11			
Windows Wkst	192.168.40.12			
Spare Address	192.168.40.13 To 192.168.40.254			

In Scope Machines

Palo Alto	Eth 1 / 1: 192.12.206.133	Eth 1 / 2: 192.168.20.1	Transit: 10.0.0.1 255.255.255.252	Management: 192.168.20.3
Ubutnu Ecom	192.168.20.9			
Fedora Webmail	192.168.20.10			
Oracle Splunk	192.168.20.11			
Ubuntu Wkst	192.168.20.12			
Cisco Firewall	Eth 1 / 1: 192.12.206.134	Eth 1 / 2: 192.168.40.1	Transit: 10.0.0.2 255.255.255.252	Management: 192.168.40.3
AD/DNS	192.168.40.9			
Web Server	192.168.40.10			
FTP Server	192.168.40.11			
Windows Wkst	192.168.40.12			

Out Of Scope Machines

(DO NOT ATTACK OR MODIFY THESE)

Proxmox Linux Server	192.168.20.4			
Linux 1	192.168.20.5			
Linux 2	192.168.20.6			
Linux 3	192.168.20.7			
Linux 4	192.168.20.8			
Spare Address	192.168.20.13 To 192.68.20.254			
Proxmox Windows Server	192.168.40.4			
Win 1	192.168.40.5			
Win 2	192.168.40.6			
Win 3	192.168.40.7			
Win 4	192.168.40.8			
Spare Address	192.168.40.13 To 192.168.40.254			

Default Credentials

In Scope

Machine	Username:Password
Palo Alto	admin:Password123
Cisco FTD	admin:!Changeme213
Windows Wkst	Administrator:Password123
Windows AD/DNS	Administrator:Password123
Windows FTP	Administrator:Password123
Windows Web	Administrator:Password123
Ubuntu Ecom	sysadmin:Password123
Fedora Webmail	root:Password123
Oracle Splunk	sysadmin:Password123
Ubuntu Wkst	sysadmin:Password123

OUT OF SCOPE DO NOT CHANGE

Machine	Username:Password
Linux 1-4 and Win 1-4	user:IURocks6767
Linux Proxmox	root:Thisismyproxmox
Windows Proxmox	root:Thisismyproxmox

Proxmox

Linux

- To access Linux Proxmox VMs, go to 192.168.20.4:8006 and log in with username and password.
- Open the console on each VM to control them.
- When VM needs to be reset, reset them to the “Vulnerable” state under Snapshots.

Name	VM Num	RAM	Snapshot
Fedora-Webmail	100	2 GiB	Vulnerable
Oracle-Splunk	101	2 GiB	Vulnerable
Ubuntu-Ecom	102	2 GiB	Vulnerable
Ubuntu-Wks	103	2 GiB	Vulnerable

Windows

- To access Windows Proxmox VMs, go to 192.168.40.4:8006 and log in with username and password.
- Open the console on each VM to control them.
- When VM needs to be reset, reset them to the “Vulnerable” state under Snapshots.

Name	VM Num	RAM	Snapshot
Win-Wkst	100	4 GiB	Vulnerable
Domain-Controller	101	6 GiB	Vulnerable
Server-2019-Web	102	4 GiB	Vulnerable
Server-2019-FTP	103	4 GiB	Vulnerable

Firewalls

Palo Alto

Interfaces:

Interface	IP Address	Security Zone
ethernet1/1	192.12.206.133/28	untrust
ethernet1/2	192.168.20.1/24	trust
ethernet1/8	10.0.0.1/30	Transit

Security Policies:

Name	Zone	Address	Dest Zone	Dest Address	Action
any2any	any	any	any	any	Allow
TransitRule	trust	192.168.20.0/24	Transit	192.168.40.0/24	Allow

NAT:

Name	Source Zone	Dest Zone	Dest Interface	Source Address	Dest Address	Source Translation	Dest Translation
Transit	trust	Transit	any	192.168.20.0/24	192.168.40.0/24	none	none
Default-NAT	any	untrust	any	any	any	Ethernet1/1 192.12.206.133/28	none

Zones:

Name	Interfaces
Transit	ethernet1/8
trust	ethernet1/2
untrust	ethernet1/1

Cisco FTD

Interfaces:

Name	Logical Name	Mode	IP Address
ethernet1/1	outside	Routed	192.12.206.134
ethernet1/2	internal	Routed	192.168.40.1
ethernet1/8	transit	Routed	10.0.0.2
Management1/1	management	Routed	192.168.40.3

Objects:

Name	Type	Value
FW1	NETWORK	192.168.20.0/24
FW1Gate	HOST	10.0.0.1
FW2	NETWORK	192.168.40.0/24
wall	HOST	192.12.206.129

Routing:

Name	Interface	Networks	Gateway IP
default	outside	0.0.0.0/0	192.12.206.129
transit	transit	192.168.20.0/24	10.0.0.1

Access Control:

Name	Action	Src Zones	Src Networks	Dst Zones	Dst Networks	Applications
AllowICMP	Allow	Any	Any	Any	Any	ICMP
TransitRule	Allow	FW2	Any	Transit	FW1	Any
AllowOutgoing	Allow	FW2	Any	outside_zone	Any	Any

NAT:

Original Packet	Translated Packet

Name	Type	Interfaces	Src Address	Dst Address	Src Address	Dst Address
TransitRule	STATIC	internal transit	FW2	FW1	FW2	FW1
DynamicNatRule	DYNAMIC	internal outside	FW2	Any	Interface	Any