CS2100 Computer Organization Tutorial 4

1. Given below are the contents of some registers and memory locations, where mem(A) refers to the data word stored in the memory location at address A:

\$s0 = 100	mem (100) =	1000
\$s1 = 160	mem (160) =	1600
\$s2 = 200	mem (200) =	2000
\$s3 = 240	mem (240) =	2400
\$s4 = 300	mem (300) =	3000
\$t0 = 10000	mem (10000) =	100
\$t1 = 15000	mem (15000) =	150
\$t2 = 20000	mem (20000) =	200
\$t3 = 25000	mem (25000) =	250
\$t4 = 30000	mem (30000) =	300

For each of the MIPS instructions below, 'op' is an unknown opcode, which is not of our concern here. For each of the data operands in the instruction, if the format is legal, give its **memory address** (if applicable) and the content inside. Note that \$s0, ..., \$s4, \$t1, ..., \$t4 are symbolic register names, \$zero is register 0 with content zero inside, and only the three addressing modes (register, immediate, and displacement) mentioned in class are considered as legal.

- (a) op \$t1, \$t2
- (b) op \$s2, 100(\$zero)
- (c) op \$t4, 40(\$s2)
- (d) op \$s3, 200(\$zero)
- (e) op \$t3, \$zero(\$t1)
- (f) op \$s1, 140(\$s1)

The answers for (a) have been done for you.

	Operand	Target Memory Address	Content
(a)	\$t1 \$t2	Not applicable Not applicable	15000 20000
(b)	\$s2 100(\$zero)		
(c)	\$t4 40(\$s2)		
(d)	\$s3 200(\$zero)		
(e)	\$t3 \$zero(\$t1)		
(f)	\$s1 140(\$s1)		

For question 2 below, we are exploring four different types of ISAs. MIPS belongs to the *Register-Register* style.

2. You are tasked to design a dedicated 16-bit processor to perform simple addition and would like to evaluate the design using the four different instruction set architecture (ISA) styles. For each of these architectures, the corresponding data movement and arithmetic operations are shown below. Note that the operands for the instructions are annotated with either @ for address, or \$ for register.

ISA	Instructions	Explanation	
Stack	push @src	Load value in @src onto top of stack.	
	pop @dest	Transfer value at top of stack to @dest.	
	Remove top two values in stack, add them, and load the sum onto top of st		
Accumulator	load @src	Load value in @src into accumulator.	
	add @src	Add value in @src and value in	
	accumulator, and put sum back into		
	accumulator.		
	store @dest Store the value in accumulator into		
		@dest.	
Memory-Memory	add @dest, @src1, @src2	Add values in @src1 and @src2, and put	
		the sum into @dest.	
Register-Register	load \$reg, @src	Load value in @src into \$reg.	
	add \$dest, \$src1, \$src2	Add values in \$src1 and \$src2, and put sum into \$dest.	
	store \$reg, @dest	Store value in \$reg into @dest.	

Consider the following three C statements with integer variables a0, a1 and a2:

For each of the four architectural styles above, write the assembly code corresponding to the above C code. Assume that the values of a0, a1, a2 are pre-assigned to memory in addresses @a0, @a1, @a2 respectively. The registers are denoted by \$r0 to \$r4. First part of each code is given.

Stack	Accumulator	Memory-Memory	Register-Register
push @a1	load @a1	add @a0, @a1, @a2	load \$r1, @a1
push @a2	add @a2		
add			

3. This is a follow up on question 2. We studied the assembly code generated for four different storage architectures, namely stack, accumulator, memory-memory and register-register. For your reference, the code fragment corresponds to the following high level statements:



(a) Let us study the instruction encoding for this question. Assume that 3 bits will be used for the opcode, and minimal space will be used to represent 128 bytes of addressable memory. Moreover, for the Register-Register ISA, there are only 5 general-purpose registers available. Assume also a fixed-length instruction format, and that the memory is byte-addressable.



For each of the four architectures, what is the number of bits required for the longest instruction? Hence, what is the size, in number of bytes, of the instructions?

Partial answers are given below. Discuss.

Number of bits for longest instruction Number of bytes	
10 2	Stack
10 2	Accumulator
4 =	Memory-Memory
	Register-Register
	Memory-Memory

- (b) What is the size (in number of bytes) of the code in question 2 for each of the four architectures? Which architecture is most efficient in terms of code size for this code?
- 4. [Past-year's exam question]

An ISA has 16-bit instructions and 5-bit addresses. There are two classes of instructions: class *A* instructions have one address, while class *B* instructions have two addresses. Both classes exist and the encoding space for opcode is completely utilized.

- (a) What is the minimum total number of instructions?
- (b) What is the maximum total number of instructions?