


Setup



```
Router>en
Router>enable
Router#conf
Router#configure ter
Router#configure terminal
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#int
Router(config)#interface g0/0
Router(config-if)#ip nat inside
Router(config-if)#
ip_ifnat_modified: old_if 2, new_if 0

Router(config-if)#no shut
Router(config-if)#exit
Router(config)#
Router(config)#
```

```

Router(config-if)#no shut
Router(config-if)#exit
Router(config)#
Router(config)#int
Router(config)#interface g0/1
Router(config-if)#ip nat outside
Router(config-if)#
ip_ifnat_modified: old_if 2, new_if 1

Router(config-if)#no shu
Router(config-if)#no shutdown
Router(config-if)#exit
Router(config)#
Router(config)#

```

Router(config) # access-list 1 permit 192.168.1.0 0.0.0.255
 Router(config) # ip nat inside source list 1 interface g0/1 overload

```

Router(config-if)#no shu
Router(config-if)#no shutdown
Router(config-if)#exit
Router(config)#
Router(config)#
Router(config)#access
Router(config)#access-list 1 per
Router(config)#access-list 1 permit 192.168.1.0 0.0.0.255
Router(config)#
Router(config)#ip nat inside source list 1 inte
Router(config)#ip nat inside source list 1 interface g0/1 over
Router(config)#ip nat inside source list 1 interface g0/1 overload
Router(config)#ipnat_add_dynamic_cfg: id 1, flag 5, range 0

id 1, flags 0, domain 0, lookup 0, aclnum 1 ,
      aclname 1 , mapname idb 7DBB26F5

Router(config)#end
Router#
%SYS-5-CONFIG_I: Configured from console by console

Router#wr
Building configuration...
[OK]
Router#

```

Cisco Packet Tracer PC Command Line 1.0

C:\>ping 203.0.113.10

Pinging 203.0.113.10 with 32 bytes of data:

Reply from 203.0.113.10: bytes=32 time<1ms TTL=127

Reply from 203.0.113.10: bytes=32 time<1ms TTL=127

Reply from 203.0.113.10: bytes=32 time<1ms TTL=127

Reply from 203.0.113.10: bytes=32 time<1ms TTL=127

Ping statistics for 203.0.113.10:

Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),

Approximate round trip times in milli-seconds:

Minimum = 0ms, Maximum = 0ms, Average = 0ms

C:\>

```
Router#show ip nat translations
Pro Inside global      Inside local      Outside local      Outside global
icmp 203.0.113.1:6      192.168.1.10:6    203.0.113.10:6     203.0.113.10:6
icmp 203.0.113.1:6      192.168.1.10:6    203.0.113.10:6     203.0.113.10:6
icmp 203.0.113.1:7      192.168.1.10:7    203.0.113.10:7     203.0.113.10:7
icmp 203.0.113.1:8      192.168.1.10:8    203.0.113.10:8     203.0.113.10:8
```

Router#