

Copilot Connectors — Start Here

How to use this documentation set before you deploy, monitor or support any connector.

What these connectors do

Microsoft 365 Copilot only sees Microsoft 365 data by default. These five **Copilot Graph connectors** each bring one external system into Copilot and Search answers — with the source system's own access rules enforced, so users only ever see what they are allowed to see.

The five connectors at a glance

Connector	Source system	What it brings to Copilot	Freshness	Sensitivity
Salesforce	Salesforce CRM	Accounts, contacts, opportunities, cases, custom objects	Live	Customer data
Clarizen	Planview AdaptiveWork	Projects, tasks, financial records	Near-real-time (webhooks)	Financial
Seismic	Seismic enablement	Documents, pages, LiveDocs (versioned)	Near-real-time	Content (MNPI-filtered)
Altrata	Altrata licensed feed	Wealth & relationship profiles on people	Feed (nightly)	HIGH — personal data (DSAR)
Hadoop BDH	BDH data mart	Salesforce mirror, at 150M+ scale	~24h lag	Customer data

Read in this order

- 1. **Tenant & Common Concepts Guide** (00) — read this first. It explains every shared idea (Copilot, Microsoft Graph, identity/ACLs, the connector engine, security, tenant limits, deployment, monitoring, disaster recovery) once, so the connector guides stay short.
- 2. **The guide for your connector** (01–05) — source-specific setup, monitoring and troubleshooting.
- 3. **The matching quick-reference card** (this PDF set) — keep it open while you work.

Before you touch anything — universal pre-flight

Collect these for **every** connector (each connector guide lists its own source-specific extras):

Universal values to request

Value / setting	Ask from
Entra Directory (tenant) ID	Entra tenant admin
One app registration per connector (5 total) + a credential (client secret or certificate)	Entra tenant admin / PKI
Azure Key Vault URI + get-secret access for the service account	Key Vault / platform team
Windows Server host(s) + a service account (log-on-as-service) and file ACLs on state/dead-letter folders	Server / AD team
Network egress to the source system and to Microsoft Graph; proxy/CA details if TLS is inspected	Network / firewall team
State store choice (SQLite or SQL Server) and the high-availability plan	DBA / platform team
A separate Graph connection for Hadoop BDH (must not share Salesforce's)	Connector operator

Bank-grade hardening release: the connectors ship privacy- and compliance-safe by default — dead-letter records are redacted, entitlements re-sync on incremental crawls, state directories are owner-only, and (where a connector has webhooks) inbound posts require a signed timestamp. Optional controls — classification-enforced ACLs, item TTL, a tamper-evident decision ledger and (Altrata) purpose-of-use authorization — are off/opt-in unless you enable them. Each connector guide's Configuration reference lists the exact variables and defaults.

Stay within the tenant's shared Graph limits (30 connections, 50M indexed items). The fleet allocation, crawl-stagger schedule and change-control rules are in the Common Guide, section 8, and in TENANT_GOVERNANCE.md.

Folder contents: 00 Common Guide · 01 Salesforce · 02 Clarizen · 03 Seismic · 04 Altrata · 05 Hadoop BDH (full .docx guides) + matching QuickRef PDFs. Full detail always lives in the .docx guides.