How to install a Minecraft Dedicated Server

Table of Contents

- How to install a Minecraft Dedicated Server
 - Table of Contents
 - Project Description
 - Requirements
 - Virtual Machine Specs
 - Setting Up The Server Environment
 - Getting your VM ready
 - Step 1 Updating your server
 - Step 2 Installing Java
 - Step 3 Creating a user account for minecraft server
 - Step 4 Creating a Minecraft server directory
 - Step 5 Download & Configure Minecraft Server
 - Step 6 Install & Configure Screen
 - Step 7 Configuring the firewall
 - Configuring the Minecraft Client
 - Step 8 Installing/Configuring to the Minecraft client

Project Description

In this document, I will demonstrate how to install and configure a Minecraft dedicated server on a Linux Distribution. Linux is a perfect choice for establishing a Minecraft server since it is known for its stability and reliability for server support. The Linux distribution I have chosen is Ubuntu 20.04 LTS. Follow along as we will give you a step by step procedure of setting up and running your Minecraft server.

Requirements

For this project we will need to have a virtual machine hosted on a Windows 10 Pro Operating System.

Requirements for my configuration

- A Virtual Machine application
- Linux Distribution: Ubuntu Server 20.04
- A Minecraft account with access to the Java Edition
- · An Active internet connection

The virtual machine I used was created with VM Virtualbox in a Windows 10 Pro desktop. If you need help setting up a VM using virtualbox, follow this tutorial.

Virtual Machine Specs

The minimum hardware recommendation for a server hosting 3-5 players:

Minimum Requirements

My Configuration

Minimum Requirements	My Configuration
RAM: 5 GB RAM	5 GB RAM
CPU: Intel core-based CPU @ 2.0 GHz and better	Intel Core i5-3570K @ 3.40 GHz
HDD: 18 GB empty space	20 GB empty space

Check out other minimum requirements for different dedicated builds

Setting Up The Server Environment

Getting your VM ready

We will be installing a GUI and Java as well as other softwares we will need to successfully implement the Minecraft server.


Step 1 - Updating your server

As a rule of thumb, ensure your Ubuntu OS is up-to-date before installing new packages. If you installed Ubuntu Server and booted the VM up. Once you log into your user account, you will be on the Ubuntu terminal. Execute the following commands.

sudo apt update sudo apt upgrade

• Installing a GUI (Optional) We will be installing the Ubuntu Desktop User Interface by executing the following command.

sudo apt-get install ubuntu-desktop



Step 2 - Installing Java

A Minecraft server will require Java Runtime Environment. OpenJDK is an open source codebase that almost all other JDKs are built on. For this project we will be using openjdk-8 Java. Execute the following commands.

sudo apt install openjdk-8-jdk

josh@linux–minecraft–server:~\$ sudo apt install openjdk–8

You can confirm the version of Java running by executing the following command. java -version

```
josh@linux-minecraft–server:~$ java –version
openjdk version "1.8.0_292"
OpenJDK Runtime Environment (build 1.8.0_292–8u292–b10–0ubuntu1~20.04–b10)
OpenJDK 64–Bit Server VM (build 25.292–b10, mixed mode)
josh@linux–minecraft–server:~$
```

Step 3 - Creating a user account for minecraft server

replace "enter_username" with you own user name

- We will be creating a minecraft user for the server sudo adduser enter_username
- Adding account to sudo group sudo usermod -aG sudo enter username
- Switching to the new user account for minecraft server su enter username

```
josh@linux–minecraft–server:~$ su – g33kh3ro
Password:
To run a command as administrator (user "root"), use "sudo <command>".
See "man sudo_root" for details.
```

Step 4 - Creating a Minecraft server directory

Now we will be creating a Minecraft directory to store all of our Minecraft files. Execute the following command to create the directory.

mkdir Minecraft

```
g33kh3ro@linux–minecraft–server:~$ mkdir minecraft
```

We will be downloading the Minecraft server file to this new directory. Change to the Minecraft directory by executing the following command.

cd Minecraft

Step 5 - Download & Configure Minecraft Server

Downloading Minecraft server Check on https://www.minecraft.net/en-us/download/server for the latest version

• Version at the time of this document is version 1.16.5.

To download directly from the terminal, execute the following command wget -0 server.jar https://launcher.mojang.com/v1/objects/1b557e7b033b583cd9f66746b7a9ab1ec1673ced/server.jar

The file will download with "server.jar" as its name. Rename the file to match its version with the following command

```
mv server.jar minecraft_server_1.16.jar
```

We will make the .jar file executable by executing the following command

```
sudo chmod +x minecraft.server 1.16.jar
```

Now we can execute the .jar file

```
java -Xmx1024M -Xms1024M -jar minecraft.server 1.16.jar
```

• We are specifying how much memory we want the file to use and the max memory we are allowing it to use. In this case we are setting both at 1 GB RAM.

We will get an initial error (Shown below)

```
g33kh3ro@linux-minecraft-server:~/minecraft$ java -Xmx1024M -Xms1024M -jar minecraft_server_1.16.jar_nogui
[12:10:13] [main/ERROR]: Failed to load properties from file: server.properties
[12:10:13] [main/WARN]: Failed to load eula.txt
[12:10:13] [main/INFO]: You need to agree to the EULA in order to run the server. Go to eula.txt for more info.
g33kh3ro@linux-minecraft-server:~/minecraft$ _
```

We need to accept the End User License Agreement before getting started with minecraft. The files we need to view will be generated for us in the working directory. Run the "ls" command and there should be two new files called "eula.txt" and "server.properties" in our working directory.

Using a text editor we will view the EULA.txt file.

```
nano eula.txt
```

Set the EULA parameter to true. Save and close the file.

```
GNU nano 4.8

#By changing the setting below to TRUE you are indicating your agreement to our EULA (https://accoud.
#Mon May 10 12:10:13 UTC 2021

eula=false

GNU nano 4.8

#By changing the setting below to TRUE you are indicating your agreement to our EULA (https://accoud.
#Mon May 10 12:10:13 UTC 2021

eula=true
```

Now we will view the Server properties.

```
nano server.properties
```

In this file we will only perform some of the primary configuration as listed below.

- * gamemode=survival This option sets the gameplay mode. Other options include creativity, adventure, and spectator.
- * difficulty=easy This option sets the difficulty of the game. Other options include peaceful, normal, and hard.
- * pvp=true
- * level-name=world
- * motd=joshlinuxserver: This is the name of your Minecraft server that will be listed in the servers list.

We have now configured both the eula.txt and server.properties file. But before we re-run the command to start the server, let install Screen.

Change out of the minecraft directory using the 'cd' commands

CO

Step 6 - Install & Configure Screen

Screen will enable the Minecraft server to run as a background process. By not using Screen, if you were to start the Minecraft server in the terminal and later close the terminal, that would automatically kill the server. With Screen, the server will continue to run in the background.

Execute the commands below.

• If screen is already installed, skip the install

```
sudo apt install screen
```

Launch a Screen session using the screen command.

screen

```
GNU Screen version 4.08.00 (GNU) 05–Feb–20
Copyright (c) 2018–2020 Alexander Naumov, Amadeusz Slawinski
Copyright (c) 2015–2017 Juergen Weigert, Alexander Naumov, Amadeusz Slawinski
Copyright (c) 2010–2014 Juergen Weigert, Sadrul Habib Chowdhury
Copyright (c) 2008–2009 Juergen Weigert, Michael Schroeder, Micah Cowan, Sadrul Habib Chowdhury
Copyright (c) 1993–2007 Juergen Weigert, Michael Schroeder
Copyright (c) 1987 Oliver Laumann
This program is free software; you can redistribute it and/or modify it under the terms of the GNU
General Public License as published by the Free Software Foundation; either version 3, or (at your
option) any later version.
This program is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without
even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU
General Public License for more details.
You should have received a copy of the GNU General Public License along with this program (see the
file COPYING); if not, see https://www.gnu.org/licenses/, or contact Free Software Foundation,
Inc., 51 Franklin Street, Fifth Floor, Boston, MA 02111-1301 USA.
Send bugreports, fixes, enhancements, t–shirts, money, beer & pizza to screen–devel@gnu.org
Capabilities:
-copy +remote–detach +power–detach +multi–attach +multi–user +font +color–256 +utf8 +rxvt
+builtin-telnet
```

Screen is now running. Press the space bar, and the terminal will show standard terminal window again.

Now we can re-run the following command

```
java -Xmx1024M -Xms1024M -jar minecraft_server.1.16.1.jar nogui
```

Now the Minecraft server will start preparing spawn area. Once the server has finished executed and is successfully running on the system, you will see the output below.

```
[Server thread/INFO]: Done (30.762s)! For help, type "help"
```

At this point we have Minecraft server up and running and you are in admin control panel. Type "help" command which listed options I can set from here.

In the current Minecraft session on the Terminal, use the Ctrl-A + Ctrl-D key sequence.

Now we need to identify the ID of our Minecraft session running on Screen. Run the -list command below.

screen -list

From the output we can identify the Minecraft session as 2552. To resume this session, use the -r parameter as in the command below.

• Replace #### with the servers 4 digit session number

screen -r #####

```
g33kh3ro@linux-minecraft-server:~/minecraft$ screen -r 2552
```

To log out or close the Terminal, be sure to use the sequence Ctrl-A + Ctrl-D to detach your Minecraft screen. This will keep the session running in the background.

Step 7 - Configuring the firewall

Once we have installed the required items, we now need to configure the firewall.

Since I will be using a separate VM in my network to log into the Minecraft server, I need to allow incoming connections from minecraft through port 25565 (default)

• Execute the following command to add a new firewall rule.

sudo ufw allow 25565



Now that we have the firewall configured and the necessary packages, we can now allow clients to connect to the Minecraft server.

Configuring the Minecraft Client

We will be working on another VM separate from the VM hosting the Minecraft Server.

Step 8 - Installing/Configuring to the Minecraft client

We will require Minecraft Java Edition.

You can download he .deb file from here

• Assuming the file has been downloaded to your downloads, execute the following command to install the .deb

sudo dpkg -i ~/Downloads/Minecraft.deb

• The Minecraft launcher should be visible in your applications list.



Launch the application


• Select Multiplayer on the title menu



• Select "Add Server" from the options



- Input the Minecraft server information
 - Server Name:
 - Server address: Hit done



The server should now appear on the list of servers available



You should be able to join the server.

If you check on the Minecraft server, you will see a notification stating the user as joined the game... and died in this case.

