
```
Archivo Máguina Ver Entrada Dispositivos Ayuda
osc@ubuntu:~$ cat simple.c
#include ux/init.h>
#include ux/kernel.h>
#include ux/module.h>
#include ux/hash.h>
#include <linux/gcd.h>
#include <asm/param.h>
#include ux/jiffies.h>
int simple_init(void){
  printk(KERN_INFO "Loading Kernel Module\n");
  printk(KERN_INFO "%lu\n", GOLDEN_RATIO_PRIME);
  printk(KERN_INFO "Hz; %d\nJiffies: %lu\n", HZ, jiffies);
  return 0;
void simple_exit(void){
  printk(KERN_INFO "Removing Kernel Module\n");
  printk(KERN_INFO "%lu\n", gcd(3300,24));
  printk(KERN_INFO "%lu\n", jiffies);
module_init(simple_init);
module exit(simple exit);
MODULE LICENSE("GPL");
MODULE DESCRIPTION("Simple Module");
MODULE AUTHOR("SGG");
osc@ubuntu:~$
```

Archivo Máquina Ver Entrada Dispositivos Ayuda



Jiffies: 4294901137

osc@ubuntu:~\$ Ismod | more

	Entrada Dispos	
Modu le	Size	Used by
simple	16384	Θ
ppdev	20480	0
intel_powerclamp	16384	Θ
vboxvideo	53248	1
ttm	98304	1 vboxvideo
drm_kms_helper	155648	1 vboxvideo
snd_inte18x0	40960	Θ
snd_ac97_codec	131072	1 snd_intel8x0
input_leds	16384	Θ
serio_raw	16384	Θ
joydev	20480	Θ
ac97_bus	16384	1 snd_ac97_codec
drm	364544	4 ttm,drm_kms_helper,vboxvideo
snd_pcm	106496	2 snd_ac97_codec,snd_inte18x0
8250_f intek	16384	Θ
parport_pc	32768	Θ
parport	49152	2 ppdev,parport_pc
snd_timer	32768	1 snd_pcm
fb_sys_fops	16384	1 drm_kms_helper
snd	81920	4 snd_ac97_codec,snd_inte18x0,snd_timer,snd_pcm
syscopyarea	16384	2 drm_kms_helper,vboxvideo
soundcore	16384	1 snd
sysfillrect	16384	2 drm_kms_helper,vboxvideo
sysimgblt	16384	2 drm_kms_helper,vboxvideo
vboxguest	286720	1 vboxvideo
i2c_piix4	24576	Θ
mac_hid	16384	0
ib_iser	49152	Θ
rdma_cm	49152	1 ib_iser
iw_cm	45056	1 rdma_cm
ib_cm	45056	1 rdma_cm
ib_sa	36864	2 rdma_cm,ib_cm
ib_mad	49152	
ib_core	106496	6 rdma_cm,ib_cm,ib_sa,iw_cm,ib_mad,ib_iser
ib_addr_	16384	2 rdma_cm,ib_core
More		

```
osc@ubuntu:~$ sudo rmmod simple
osc@ubuntu:~$ dmesg | tail -11
    6.8085811 IPv6: ADDRCONF(NETDEV_CHANGE): enp0s3: link becomes ready
    6.8937901 cgroup: new mount options do not match the existing superblock, will be ignored
    9.3320101 floppy0: no floppy controllers found
   35.5464801 simple: module verification failed: signature and/or required key missing - tainting
kernel
   35.5470101 Loading Kernel Module
   35.5470111 11400862456688148481
   35.5470121 Hz; 250
              Jiffies: 4294901137
  286.2394901 Removing Kernel Module
  286.2394921 12
  286.2394921 4294963810
osc@ubuntu:~$ lsmod | head -n 4
Module
                        Size Used by
ppdev
                      20480 0
intel_powerclamp
                      16384 0
vboxvideo
                      53248 1
osc@ubuntu:~$
```