
1.



2.

Physical Config Attributes

GLOBAL Settings

Display Name Home VolP0
Server Address 10.3.0.1

## IOS Command Line Interface

```
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up
Router(config-if) #exit
Router(config) #ip dhcp excluded-address 10.3.0.1
Router(config) #ip dhcp pool Telephony
Router(dhcp-config) #network 10.3.0.0 255.255.255.0
Router(dhcp-config) #default-router 10.3.0.1
Router(dhcp-config) #option 150 ip 10.3.0.1
Router (dhcp-config) #exit
Router(config) #telephony-service
Router(config-telephony) #max-ephones 10
Router(config-telephony) #max-dn 10
Router(config-telephony) #ip source-address 10.3.0.1 port 2000
Router(config-telephony) #auto assign 1 to 10
Router(config-telephony) #exit
Router(config) #telephony-service
Router(config-telephony) #ephone-dn 1
Router(config-ephone-dn)#%LINK-3-UPDOWN: Interface ephone_dsp DN 1.1, changed state to up
Router(config-ephone-dn)#number 101
Router(config-ephone-dn)#exit
Router(config)#
%IPPHONE-6-REGISTER: ephone-1 IP:10.3.0.2 Socket:2 DeviceType:Phone has registered.
Router(config) #ephone-dn 2
Router(config-ephone-dn)#%LINK-3-UPDOWN: Interface ephone_dsp DN 2.1, changed state to up
Router(config-ephone-dn)#number 102
Router(config-ephone-dn) #exit
Router(config) #ephone-dn 3
Router(config-ephone-dn)#%LINK-3-UPDOWN: Interface ephone_dsp DN 3.1, changed state to up
Router(config-ephone-dn)#number 103
Router(config-ephone-dn)#exit
Router(config) #ephone-dn 4
Router(config-ephone-dn) #%LINK-3-UPDOWN: Interface ephone dsp DN 4.1, changed state to up
Router(config-ephone-dn)#number 104
Router(config-ephone-dn)#exit
Router(config) #ephone-dn 5
Router(config-ephone-dn)#%LINK-3-UPDOWN: Interface ephone dsp DN 5.1, changed state to up
Router(config-ephone-dn) #number 105
```

