1.



```
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/2, changed state
Switch>en
Switch#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Switch(config) #int range fa0/1-2
Switch(config-if-range) #channel-group 1 mode ?
           Enable LACP unconditionally
  active
            Enable PAgP only if a PAgP device is detected
 desirable Enable PAgP unconditionally
            Enable Etherchannel only
            Enable LACP only if a LACP device is detected
 passive
Switch(config-if-range)#channel-group 1 mode on
Switch(config-if-range)#
Creating a port-channel interface Port-channel 1
%LINK-5-CHANGED: Interface Port-channell, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface Port-channell, changed state t
Switch(config-if-range)#end
Switch#
%SYS-5-CONFIG I: Configured from console by console
Switch#wr memory
Building configuration...
[OK]
Switch#
```

Physical Config Desktop Programming Attributes

```
Command Prompt
```

```
Cisco Packet Tracer PC Command Line 1.0
C:\>ping 192.168.0.2 with 32 bytes of data:

Reply from 192.168.0.2: bytes=32 time<lms TTL=128

Ping statistics for 192.168.0.2:

Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
Approximate round trip times in milli-seconds:

Minimum = 0ms, Maximum = 0ms, Average = 0ms

C:\>
```

```
4.


Switch(config) #int fa0/1
Switch(config-if) #sh

Switch(config-if) #
%LINK-5-CHANGED: Interface FastEthernet0/1, changed state to administratively down
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/1, changed state to down
```

5.



1.



2.

IOO COMMUNICINA ENTO INTEL INCO

```
Press RETURN to get started!
Switch>en
Switch#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Switch(config)#int range fa0/1-2
Switch(config-if-range) #channel-protocol lacp
Switch(config-if-range) #channel-group 1 mode active
Switch(config-if-range)#
Creating a port-channel interface Port-channel 1
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/1, changed state to down
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/1, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/2, changed state to down
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/2, changed state to up
Switch(config-if-range)#exit
Switch(config) #int range fa0/3-4
Switch(config-if-range)#channel-protocol lacp
Switch(config-if-range)#channel-group 2 mode active
Switch(config-if-range)#
Creating a port-channel interface Port-channel 2
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/3, changed state to down
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/3, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/4, changed state to down
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/4, changed state to up
Switch(config-if-range)#
```

```
Cisco Packet Tracer PC Command Line 1.0
C:\>ping 192.168.0.2

Pinging 192.168.0.2 with 32 bytes of data:

Reply from 192.168.0.2: bytes=32 time<lms TTL=128
Ping statistics for 192.168.0.2:

Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
Approximate round trip times in milli-seconds:

Minimum = 0ms, Maximum = 0ms, Average = 0ms

C:\>
```