Overview

Kaui lets you configure basic settings for how the system behaves when an account is overdue. In Kaui, this is a subset of the full overdue configuration settings and is defined at the tenant level. For more information, see the *Overdue System Guide*.



Note: You can also configure overdue actions for the *global* Kill Bill system (as opposed to configuring at the tenant level). For more information, see the *Overdue System* documentation.

See the following sections to configure overdue (dunning) flows for a tenant:

- View overdue configuration
- Configure overdue flows
- Upload an XML overdue configuration file
- View overdue configuration as XML
- Delete overdue flows

You cannot edit a raw overdue configuration XML file in Kaui.


Additional Overdue Resources

- "Overdue" section in the Subscription Guide.
- Overdue System Guide

View Overdue Configuration

If any overdue (dunning) actions are configured, you can see them on the Overdue Show tab at the bottom of the Tenant Configuration page. To get there:

1. Click on your username and tenant name in the upper right corner:



Kaui displays the Tenant Configuration page.

2. Scroll down and click on the Overdue Show tab:



Configure Overdue Flows

The following steps explain how to set up overdue flows (i.e., actions) for the tenant.

1. Go to the Overdue Show tab on the Tenant Configuration page.




2. Click the plus sign () next to **Existing Overdue Config**.

Kaui opens the Overdue Configuration screen:




3. Click + New Overdue States. Kaui opens the fields for editing:



4. Fill in the fields for the current row. For field information, see the Overdue Configuration Field

Descriptions table.

5. To add another overdue configuration row, click + **new overdue states**.



6. When you are done adding configuration rows, click the **Save** button. Kaui displays the new row(s) on the Overdue Show tab:

I NEED A SCREENSHOT OF THIS



Note: To edit an existing overdue state/action, on the Overdue Show tab, click the plus sign () next to **Existing Overdue Config.** This opens the overdue configuration fields in edit mode.


Overdue Configuration Field Descriptions

Field	Description
Name	The name assigned to the overdue flow.
External Message	Message text that other plugins, when listening for overdue events, can retrieve and display to the user. (Optional)
Block Subscription Changes	If set to true, the customer can make plan changes to the subscription in this overdue state. If set to false, the customer cannot make changes.
Subscription Cancellation	Select the option that describes how Kill Bill behaves regarding a cancellation in this overdue state: • NONE: The subscription is not cancelled. <i>Not sure this is right</i>
	 POLICY_NONE: ??? Maybe some to do with the default cancellation policy in the catalog? Not sure
	• POLICY_IMMEDIATE_POLICY: Cancels the subscription immediately and applies a partial credit to the account based on how much of the service has been consumed.
	• END_OF_TERM: Cancels the subscription at the end of the billing period with no refund to the customer (i.e., no proration).
Days Since Earliest Unpaid Invoice	Specifies how many days should pass after the last unpaid invoice before initiating this overdue flow.

Field	Description
Tag Inclusion	Specifies that the overdue flow will occur if the account is tagged with one of the selected system (control) tags. To disregard tag inclusion for this overdue state, leave as the default NONE setting.
	• AUTO_PAY_OFF
	• AUTO_INVOICING_OFF
	OVERDUE_ENFORCEMENT_OFF
	• MANUAL_PAY
	• TEST
	• PARTNER
	For a description of system tags, see the "Tags" section of the Subscription Guide.
Tag Exclusion	Specifies that the overdue flow will <i>not</i> occur if the account is tagged with one of the selected system (control) tags. See tags information above.
Number of Unpaid Invoices	Specifies that the overdue flow will occur if the number of unpaid invoices equals or exceeds the specified value.
Total Unpaid Invoice Balance	Specifies that the overdue action will occur if the total unpaid invoice balance equals or exceeds the specified value.

Upload an XML Overdue Configuration File

1. Go to the Overdue Show tab on the Tenant Configuration page.



2. Click the plus sign (🚼) next to **Existing Overdue Config**.

Kaui opens the Overdue Configuration screen:

DRAFT



3. Click **Enable Advanced Configuration (Upload XML)**. Kaui displays an upload screen:



4. Click the Choose File button, locate the XML file, and select it.

Once you have selected the file, Kaui displays the filename next to the Choose File button.




5. Click the **Upload** button.

If the upload is successful, Kaui displays a confirmation message along with a list of plans on the Catalog Show tab:

View Overdue Configuration as XML

1. Go to the Overdue Show tab on the Tenant Configuration page.




2. Click View Overdue XML.

NOT SURE WHAT HAPPENS HERE. IT DOESN'T WORK FOR ME - GOES TO MAIN HOMEPAGE


Delete Overdue Flows

1. Go to the Overdue Show tab on the Tenant Configuration page.



Kaui opens the Overdue Configuration screen.

3. Click the red X (\nearrow) to the right of every configuration row you want to delete.



4. Click the **Save** button.

Kaui removes the overdue configuration row(s) from the Overdue Show tab and displays a successful deletion message.

THIS ALSO DOESN'T WORK FOR ME. I'M ASSUMING YOU GET A CONFIRMATION MESSAGE THAT THE DELETE WORKED.