

APRS COMMAND

Beta Test Form

Platform: Raspberry Pi

Updated Edition — July 27, 2026

Covers v0.5.0-alpha+ through KISS-TCP / Serial-KISS / AGWPE integration and GrayWolf field-server connectivity

Tester Name: _____

Callsign: _____

Test Date(s): _____

Hardware / Machine Notes: _____

For each item below, check Pass, Fail, or N/A. For anything marked Fail, log it on a separate Bug Report Form with reference to the section and item number here. See the companion Bug Hunting & Testing Guide for background on why each regression-watch item matters.

Reset-to-clean-install note: Remove `~/config/APRSCommand` (confirm actual folder name against the installed build) and reinstall to return to a clean state.

1. Installation & Setup

Verify a clean install completes correctly on this platform.

#	Test Item	Pass	Fail	N/A
1	Confirm the ARM build is what actually installs and runs (not an x64 build silently failing or emulating).	☐	☐	☐
2	Confirm the desktop entry launches correctly from the Pi's application menu.	☐	☐	☐
3	Note the Pi model and RAM (e.g. Pi 4 4GB, Pi 5 8GB) being used for this test pass, since performance results depend heavily on hardware.	☐	☐	☐
4	If testing headless, confirm the app can be reached/controlled appropriately for the intended field deployment (e.g. VNC, direct HDMI, or Mobile Companion).	☐	☐	☐

2. First Run & Initial Configuration

Verify first-run behavior on a machine with no prior APRS Command settings.

#	Test Item	Pass	Fail	N/A
1	On first launch with no saved settings, the app starts without crashing (regression watch: null Callsign/BeaconPath).	☐	☐	☐
2	Callsign and BeaconPath are required before proceeding past initial setup.	☐	☐	☐
3	Default theme (Light) loads; Dark and High Contrast are selectable and persist after restart.	☐	☐	☐
4	Live station data appears shortly after launch — not old sample/design-time stations.	☐	☐	☐

3. Connections (APRS-IS, KISS-TCP, Serial-KISS, AGWPE, GrayWolf)

Verify every connection type this platform supports, individually and combined.

#	Test Item	Pass	Fail	N/A
1	Add, edit, and remove an APRS-IS server connection; confirm it connects and stations populate.	☐	☐	☐
2	Add a Network TNC KISS-TCP port pointed at a live source (e.g. Direwolf loopback or GrayWolf); confirm Enabled / Receive / Transmit toggle independently.	☐	☐	☐
3	Add a Serial-KISS port; confirm blank port names don't crash the port list.	☐	☐	☐
4	Add an AGWPE port and enable it purely through the Settings UI — confirm it actually connects (regression watch: AGWPE Enabled flag not previously set by the UI).	☐	☐	☐
5	Run APRS-IS and a KISS-TCP source at the same time; confirm packets merge with no duplicate or dropped stations.	☐	☐	☐
6	Restart the app after configuring multiple ports; confirm all settings and enabled states persisted.	☐	☐	☐

#	Test Item	Pass	Fail	N/A
7	Point a Network TNC KISS-TCP port at real GrayWolf hardware (IP:8001); confirm RF packets from GrayWolf's AFSK modem appear on the map.	☐	☐	☐
8	Test GrayWolf's digipeater passthrough — confirm digipeated packets show the correct path.	☐	☐	☐
9	Test GrayWolf's iGate passthrough — confirm RF-to-Internet gated packets are correctly tagged.	☐	☐	☐
10	Disconnect GrayWolf mid-session; confirm a clear disconnected state and clean reconnection, not a crash or hang.	☐	☐	☐

4. Map & Station Display

Verify map rendering and station tracking behave correctly.

#	Test Item	Pass	Fail	N/A
1	Stations render correctly, including course/speed/altitude for compressed-format packets.	☐	☐	☐
2	Follow-me / search-and-center works without fighting manual panning.	☐	☐	☐
3	Layer toggles show and hide the correct layers.	☐	☐	☐
4	Right-click context menus appear on stations with the expected actions.	☐	☐	☐

5. Messaging

Verify sending, receiving, and the Message Broadcast window.

#	Test Item	Pass	Fail	N/A
1	Send a message to a live station; confirm delivery/ack behavior.	☐	☐	☐
2	Receive a message; confirm correct display, including special characters.	☐	☐	☐
3	Message Broadcast window opens without crashing (regression watch: MainWindowViewModel accessor).	☐	☐	☐

6. Beaconing

Verify manual and scheduled beaconing, including compressed position format.

#	Test Item	Pass	Fail	N/A
1	Manual beacon send works from a clean configuration.	☐	☐	☐
2	Scheduled beaconing fires at the configured interval.	☐	☐	☐
3	Compressed position beacons (course, speed, altitude, radio range) parse correctly on the receiving end.	☐	☐	☐

7. Radar

Verify Radar opens, animates, and its controls behave correctly.

#	Test Item	Pass	Fail	N/A
1	Radar window opens and tiles load.	☐	☐	☐
2	Animation plays without a stuck frame (regression watch: StopAnimation()).	☐	☐	☐
3	Scrubber control appears and is usable during animation (regression watch: missing PropertyChanged).	☐	☐	☐
4	Sidebar icon highlights while active; menu item label reflects live ON/OFF state.	☐	☐	☐

8. Weather / NWS Alerts

Verify the alerts window and weather packet parsing.

#	Test Item	Pass	Fail	N/A
1	NWS Alerts window opens and has a working Close button (regression watch).	☐	☐	☐
2	A positionless weather packet with an MDHM timestamp decodes correctly (regression watch).	☐	☐	☐

9. Net Control

Verify the Net Control window.

#	Test Item	Pass	Fail	N/A
1	Net Control window opens and has a working Close button (regression watch).	☐	☐	☐

10. After-Action Export

Verify export functionality and window stability.

#	Test Item	Pass	Fail	N/A
1	Window opens without crashing (regression watch: MainWindowViewModel accessor).	☐	☐	☐
2	Export produces a valid, openable file with correct session data.	☐	☐	☐

11. Coverage Prediction

Verify window stability.

#	Test Item	Pass	Fail	N/A
1	Window opens without crashing (regression watch: MainWindowViewModel accessor).	☐	☐	☐

12. GPX/KML & CalTopo/SARTopo

Verify track import/export and live position forwarding.

#	Test Item	Pass	Fail	N/A
1	Import a GPX track; confirm correct placement on the map (EPSG:3857 conversion).	☐	☐	☐
2	Import a KML track; confirm the same.	☐	☐	☐
3	Export a track, re-import it, and confirm round-trip fidelity.	☐	☐	☐
4	Enable CalTopo/SARTopo live position forwarding; confirm positions appear correctly and promptly.	☐	☐	☐
5	Disable forwarding; confirm it actually stops.	☐	☐	☐

13. Mobile Companion Server

Verify phones on the same LAN can actually connect (regression watch).

#	Test Item	Pass	Fail	N/A
1	Enable Mobile Companion Server and connect from an actual phone on the same LAN, not just localhost.	☐	☐	☐
2	Confirm live station and message data reaches the phone.	☐	☐	☐

14. Software Updates & Stability Testing

Verify update behavior and run extended-session stability checks specific to this platform.

#	Test Item	Pass	Fail	N/A
1	On startup with internet access, the app checks for an update.	☐	☐	☐
2	With no internet access, the check fails silently — no error dialog, no crash.	☐	☐	☐
3	When an update is available, the Velopack auto-install path completes and the app relaunches on the new version.	☐	☐	☐
4	Every secondary window (Net Control, NWS Alerts, Radar, After-Action Export, Message Broadcast, Coverage Prediction, Connections) has a working Close button.	☐	☐	☐
5	Closing the main window closes or properly orphans all secondary windows — no zombie windows left running.	☐	☐	☐
6	Watch CPU and memory usage specifically during Radar animation and multi-port connections — the Pi's limited resources are the most likely place a problem shows up that doesn't appear on a laptop or desktop.	☐	☐	☐
7	Run an extended session on battery power paired with real GrayWolf hardware (this is the primary field-deployment pairing) and watch for dropped connections, thermal throttling, or slowdowns over time.	☐	☐	☐
8	Test recovery from a lost Wi-Fi/network link to GrayWolf or APRS-IS — confirm the app reconnects cleanly rather than requiring a restart.	☐	☐	☐

Notes / Additional Findings:
