
## **INSTALLATION DE PYZO - BCPST**


Il est vivement conseillé de désinstaller toutes les versions précédentes de Python et de Pyzo. L'utilisation de Pyzo ne nécessite pas l'installation de Python.

Télécharger: Pyzo et Anaconda sur http://www.pyzo.org/start.html#quickstart.

**Installer: Pyzo** avec les paramètres suivants.




Installer ensuite Anaconda avec les paramètres suivants.




## Stéphane KELLER – Lycée agricole Louis Pasteur

Lancer Pyzo. Le message d'erreur suivant apparaît dans le shell (console).



## Dans le menu **Shell** ; **Configuration des Shells**.

Dans la ligne exe, choisir ...\anaconda3\python.exe ...



## Done

Cliquer dans le shell sur 💈 pour redémarrer le shell.

Installation des modules : les modules sont déjà préinstallés avec Anaconda.

```
>>> pip install numpy
Requirement already satisfied: num
py in c:\users\bureau\anaconda3\li
b\site-packages
>>> pip install matplotlib
Requirement already satisfied: mat
plotlib in c:\users\bureau\anacond
a3\lib\site-packages
Requirement already satisfied: num
py>=1.7.1 in c:\users\bureau\anaco
nda3\lib\site-packages (from matpl
otlib)
Requirement already satisfied: six
>=1.10 in c:\users\bureau\anaconda
3\lib\site-packages (from matplotl
ib)
Requirement already satisfied: pyt
hon-dateutil>=2.0 in c:\users\bure
au\anaconda3\lib\site-packages (fr
om matplotlib)
Requirement already satisfied: pyt
z in c:\users\bureau\anaconda3\lib
\site-packages (from matplotlib)
Requirement already satisfied: cyc
ler>=0.10 in c:\users\bureau\anaco
nda3\lib\site-packages (from matpl
otlib)
Requirement already satisfied: pyp
arsing!=2.0.4,!=2.1.2,!=2.1.6,>=2.
0.1 in c:\users\bureau\anaconda3\l
ib\site-packages (from matplotlib)
>>> pip install pillow
Requirement already satisfied: pil
low in c:\users\bureau\anaconda3\l
ib\site-packages
Requirement already satisfied: ole
file in c:\users\bureau\anaconda3\
lib\site-packages (from pillow)
```

>>>

Installation Pyzo BCPST