

Arduino code:

```
#include <Wire.h>
#include <Adafruit_GFX.h>
#include <Adafruit_SSD1306.h>
#include <SoftwareSerial.h>
#include <DFRobotDFPlayerMini.h>

#define SCREEN_WIDTH 128
#define SCREEN_HEIGHT 64

Adafruit_SSD1306 display(SCREEN_WIDTH, SCREEN_HEIGHT, &Wire,
-1);

// SoftwareSerial pins: RX, TX (change if needed)
SoftwareSerial mySerial(10, 11);
DFRobotDFPlayerMini myDFPlayer;

void showMessage(const String &text) {
  display.clearDisplay();
  display.setTextSize(2);
  display.setTextColor(WHITE);
  display.setCursor(0, 20);
  display.println(text);
  display.display();
}

void setup() {
  Serial.begin(9600);    // USB serial for debugging
  mySerial.begin(9600);  // DFPlayer serial

  if (!display.begin(SSD1306_SWITCHCAPVCC, 0x3C)) {
    // If display init fails, halt (or continue without display)
    while (true);
  }
  display.clearDisplay();
  display.display();
```

```

showMessage("Ready...");

if (!myDFPlayer.begin(mySerial)) {
  showMessage("DF Error!");
  while (true);
}

myDFPlayer.volume(25); // 0..30
}

void loop() {
  // Read full line terminated by newline from Python script
  if (Serial.available()) {
    String s = Serial.readStringUntil('\n');
    s.trim();
    if (s.length() == 0) return;

    int finger = s.toInt(); // converts "10" -> 10, "5" -> 5

    Serial.print("Received: ");
    Serial.println(finger);

    switch (finger) {
      case 1:
        showMessage("I want die");
        myDFPlayer.play(1);
        break;
      case 2:
        showMessage("I Need Food");
        myDFPlayer.play(2);
        break;
      case 3:
        showMessage("I Need Help");
        myDFPlayer.play(3);
        break;
      case 4:
        showMessage("Washroom Please");
        myDFPlayer.play(4);

```

```
        break;
    case 5:
        showMessage("Not Feeling Well");
        myDFPlayer.play(5);
        break;
    case 6:
        showMessage("Call Doctor");
        myDFPlayer.play(6);
        break;
    case 7:
        showMessage("Call Family");
        myDFPlayer.play(7);
        break;
    case 8:
        showMessage("Turn Fan ON");
        myDFPlayer.play(8);
        break;
    case 9:
        showMessage("Close Door");
        myDFPlayer.play(9);
        break;
    case 10:
        showMessage("EMERGENCY");
        myDFPlayer.play(10);
        break;
    default:
        showMessage("Unknown");
        break;
}
}
}
```