```
Cambiamos el nombre y lo comprobamos, reiniciamos y comprobamos otra vez
a@a-VirtualBox:~$ sudo hostnamectl set-hostname equipo linux
[sudo] password for a:
a@a-VirtualBox:~$ hostname
equipolinux
a@a-VirtualBox:~$
Ping al equipo
a@equipolinux:~$ ping equipolinux
PING equipolinux (fd00::a00:27ff:fe59:3161) 56 data bytes
64 bytes from equipolinux (fd00::a00:27ff:fe59:3161): icmp_seq=1 ttl=64 time=0.0
64 bytes from equipolinux (fd00::a00:27ff:fe59:3161): icmp_seq=2 ttl=64 time=0.0
Ping a localhost ipv6 y loopback
                         1 localhost && ping -c 1 ::1 && ping -c1 127.0.0.1
PING localhost (127.0.0.1) 56(84) bytes of data.
64 bytes from localhost (127.0.0.1): icmp seq=1 ttl=64 time=0.024 ms
--- localhost ping statistics ---
1 packets transmitted, 1 received, 0% packet loss, time 0ms
rtt min/avg/max/mdev = 0.024/0.024/0.024/0.000 ms
PING ::1 (::1) 56 data bytes
64 bytes from ::1: icmp_seq=1 ttl=64 time=0.014 ms
--- ::1 ping statistics ---
1 packets transmitted, 1 received, 0% packet loss, time 0ms
rtt min/avg/max/mdev = 0.014/0.014/0.014/0.000 ms
PING 127.0.0.1 (127.0.0.1) 56(84) bytes of data.
64 bytes from 127.0.0.1: icmp seq=1 ttl=64 time=0.010 ms
--- 127.0.0.1 ping statistics ---
1 packets transmitted, 1 received, 0% packet loss, time 0ms
rtt min/avg/max/mdev = 0.010/0.010/0.010/0.000 ms
Paramos y deshabilitamos el network manager, reiniciamos y comprobamos
n@equipolinux:~$ sudo systemctl stop NetworkManager
[sudo] password for a:
```

```
a@equipolinux:~$ sudo systemctl stop NetworkManager
[sudo] password for a:
a@equipolinux:~$ sudo systemctl disable NetworkManager
Removed "/etc/systemd/system/dbus-org.freedesktop.nm-dispatcher.service".
Removed "/etc/systemd/system/network-online.target.wants/NetworkManager-wait-online.service".
Removed "/etc/systemd/system/multi-user.target.wants/NetworkManager.service".
```

Volvemos a habilitarlo

```
a@equipolinux:~$ ip a
1: lo: <LOOPBACK,UP,LOWER_UP> mtu 65536 qdisc noqueue state UNKNOWN group defaul
t qlen 1000
    link/loopback 00:00:00:00:00:00 brd 00:00:00:00:00:00
    inet 127.0.0.1/8 scope host lo
       valid_lft forever preferred_lft forever
    inet6 ::1/128 scope host noprefixroute
       valid_lft forever preferred_lft forever
2: enp0s3: <BROADCAST,MULTICAST> mtu 1500 qdisc noop state DOWN group default ql
en 1000
    link/ether 08:00:27:59:31:61 brd ff:ff:ff:ff:ff
a@equipolinux:~$ sudo systemctl enable NetworkManager
[sudo] password for a:
Created symlink /etc/systemd/system/multi-user.target.wants/NetworkManager.servi
ce → /usr/lib/systemd/system/NetworkManager.service.
Created symlink /etc/systemd/system/dbus-org.freedesktop.nm-dispatcher.service
/usr/lib/systemd/system/NetworkManager-dispatcher.service.
Created symlink /etc/systemd/system/network-online.target.wants/NetworkManager-w
ait-online.service \rightarrow /usr/lib/systemd/system/NetworkManager-wait-online.service.
a@equipolinux:~$ sudo systemctl start NetworkManager
a@equipolinux:~$
```