


Configuring User Workspaces

- What is a user type?
- When & why would you configure user workspaces?
- Who has permission/ability to do this?
- Where is this done in Sakai?
- Step-by-Step: How to configure a user workspace




Properties of a user type

- Everyone who logs in is assigned ONE user type
 - registered
 - maintain
 - guest
 - [default user type has no name]



- User logs in -> Sakai checks user's type -> Sakai creates a new workspace for the user
- User logs in -> Sakai checks user's type -> Sakai gives user some system permissions
- User logs in -> Sakai checks user's type -> Sakai gives user some workspace permissions
- An user's type can be changed. But.





When and Why should you configure or reconfigure user workspaces?

- Upon initial implementation
- During an upgrade/when new workspace tools become available
 - Ex. replacing Profile with Profile2
- Whenever you decide you don't like them anymore
- When changes to business process require it





Who configures workspaces?

 Collaborative effort between the Sakai functional administrator and the Sakai systems administrator








Where in Sakai do admins configure workspaces?

- Admin Workspace Sites tool
- Admin Workspace Realms tool
- In the database





How to configure a user workspace

- Step 1: Gather your decision makers and decide on a toolset and order
- Step 2: Configure user template sites
- Step 3: Configure !user.template realms
- Step 4: Configure !user realm (optional)
- Step 5: Reorder workspace tools (optional)
- Step 6: Submit a ticket to ANI support asking them to reset your user workspaces



What does ANI support do with your workspace reset request?

Something like this (do NOT try this at home or on Oracle):

delete from SAKAI_SITE_TOOL_PROPERTY where SITE_ID like '~%' and SITE_ID != '~admin'; delete from SAKAI_SITE_TOOL where SITE_ID like '~%' and SITE_ID != '~admin'; delete from SAKAI_SITE_PAGE_PROPERTY where SITE_ID like '~%' and SITE_ID != '~admin'; delete from SAKAI_SITE_PAGE where SITE_ID like '~%' and SITE_ID != '~admin'; delete from SAKAI_SITE_USER where SITE_ID like '~%' and SITE_ID != '~admin'; delete from SAKAI_SITE_GROUP_PROPERTY where SITE_ID like '~%' and SITE_ID != '~admin'; delete from SAKAI_SITE_GROUP where SITE_ID like '~%' and SITE_ID != '~admin'; delete from SAKAI_SITE_PROPERTY where SITE_ID like '~%' and SITE_ID != '~admin'; delete from SAKAI_SITE_Where SITE_ID like '~%' and SITE_ID != '~admin';

This is Kenny. He runs the script.



DELETE SAKAI_REALM_RL_FN FROM SAKAI_REALM_RL_FN INNER JOIN SAKAI_REALM ON SAKAI_REALM_RL_FN.REALM_KEY = SAKAI_REALM.REALM_KEY AND SAKAI_REALM.REALM_ID like '/site/~%' and SAKAI_REALM.realm_id != '/site/~admin';

DELETE SAKAI_REALM_RL_GR FROM SAKAI_REALM_RL_GR INNER JOIN SAKAI_REALM ON SAKAI_REALM_RL_GR.REALM_KEY = SAKAI_REALM.REALM_KEY AND SAKAI_REALM.REALM_ID like '/site/~%' and SAKAI_REALM.REALM_ID != '/site/~admin';

DELETE SAKAI_REALM_PROVIDER FROM SAKAI_REALM_PROVIDER INNER JOIN SAKAI_REALM ON SAKAI_REALM_PROVIDER.REALM_KEY = SAKAI_REALM_REALM_KEY AND SAKAI_REALM_REALM_ID like '/site/~%' and SAKAI_REALM_REALM_ID != '/site/~admin';

DELETE SAKAI_REALM_ROLE_DESC FROM SAKAI_REALM_ROLE_DESC INNER JOIN SAKAI_REALM ON SAKAI_REALM_ROLE_DESC.REALM_KEY = SAKAI_REALM_REALM_KEY AND SAKAI_REALM.REALM_ID like '/site/~%' and SAKAI_REALM.REALM_ID != '/site/~admin';

DELETE SAKAI_REALM_PROPERTY FROM SAKAI_REALM_PROPERTY inner join SAKAI_REALM ON SAKAI_REALM_PROPERTY.REALM_KEY = SAKAI_REALM_RE



Questions and Answers

Contact:

Jim Mezzanotte: jmezzanotte@anisakai.com

Kara Stiles: kstiles@anisakai.com