

Running Commands Guide

All commands needed to set up and run the system — generated 16 August 2026

1. One-Click Start

Double-click **run.bat** in the project folder, or run it from the command line. It activates the virtual environment, installs dependencies on first run, applies pending migrations and starts the server on <http://127.0.0.1:8000>.

2. First-Time Setup

Step	Command	What it does
Virtual env	<code>python -m venv venv</code>	Create an isolated environment
Activate	<code>venv\Scripts\activate</code>	Switch into the environment
Install	<code>pip install -r requirements.txt</code>	Install all dependencies
Env config	<code>copy .env.example .env</code>	Create your config file
Database	<code>python manage.py migrate</code>	Create all database tables
Seed data	<code>python manage.py seed_demo_data</code>	Create departments, users, subjects, students
Start	<code>python manage.py runserver</code>	Start the dev server

3. Common Management Commands

Task	Command
Run all tests	<code>python manage.py test --settings=config.settings.testing</code>
Run tests for one app	<code>python manage.py test accounts --settings=config.settings.testing</code>
Check project health	<code>python manage.py check</code>
Make migrations	<code>python manage.py makemigrations</code>
Apply migrations	<code>python manage.py migrate</code>
Create a staff user	<code>python manage.py seed_demo_data --password YourPass123</code>
Create superuser	<code>python manage.py createsuperuser</code>
Generate PDFs	<code>python manage.py generate_pdfs</code>
Collect static files	<code>python manage.py collectstatic</code>

4. Server Options

Command	Effect
<code>python manage.py runserver</code>	Default server on http://127.0.0.1:8000
<code>python manage.py runserver 0.0.0.0:8000</code>	Listen on all interfaces (LAN access)
<code>python manage.py runserver --noreload</code>	Run without auto-restart on code changes
<code>python manage.py runserver 8080</code>	Use a different port

5. Logins After Seeding

All seeded accounts use the password **RG CET@2026**. Log in at <http://127.0.0.1:8000/accounts/login/> with **admin** (Super Admin) or a HOD/teacher account such as **hod_cse**. See USER_CREDENTIALS.pdf for the full list.