DATE:27.08.2024

ROLLNO:231901503

# **Customize Switch with Network Modules using Cisco Packet Tracer**

#### AIM:

To Customize Switch with Network Modules using Cisco Packet Tracer

# 1. Open Cisco Packet Tracer

- ☐ Launch Cisco Packet Tracer on your computer.
- **2.** Add a Switch to Your Workspace 

  In the device toolbar (usually on the left side of the screen), locate the "Switches" section.
  - □ Drag and drop a switch model onto the workspace. For instance, you might choose a model like the "2950" or "2960."

### 3. Access the Switch's Physical Layout

- Click on the switch in the workspace to open its configuration window.
- Navigate to the "Physical" tab to see the switch's physical layout and modules.
- **4. Add Network Modules** In the "Physical" tab, you might see options to add or modify network modules.
  - Click on the slot where you want to add a module. You can choose from available modules such as different types of Ethernet or Fiber modules.
  - Drag the module from the list of available modules and drop it into the slot on the switch.
- **5.** Configure the Modules 

  After adding the module, switch to the "Config" tab in the switch's configuration window.
  - Here, you can configure the ports provided by the module. For example, you can set IP addresses, VLAN configurations, and other settings for the new interfaces.

## 6. Configure the Switch Ports

• Switch to the "Config" tab to configure ports on the switch. Here, you can set parameters for each port.

- Select the specific port or range of ports you want to configure. You can set parameters such as VLAN assignments, port descriptions, and more.
- For example: o To configure a port to be in a specific VLAN:
  - Select the port or range of ports.
  - ☐ Assign the VLAN ID under the VLAN settings. To set a

description for the port:

☐ Enter a description in the "Description" field.

## 7. Using the CLI for Detailed Configuration

- Switch to the "CLI" tab for command-line interface access.
- Enter configuration commands to set up the switch. Here's an example of how to configure VLANs and interface settings via CLI:

```
bash
                                                                           (T) Copy code
Switch> enable
Switch# configure terminal
! Configure VLAN
Switch(config)# vlan 10
Switch(config-vlan)# name Sales
Switch(config-vlan)# exit
! Configure VLAN interface
Switch(config)# interface vlan 10
Switch(config-if)# ip address 192.168.10.1 255.255.255.0
Switch(config-if)# no shutdown
Switch(config-if)# exit
! Assign ports to VLAN
Switch(config)# interface range fa0/1 - 24
Switch(config-if-range)# switchport mode access
Switch(config-if-range)# switchport access vlan 10
Switch(config-if-range)# exit
! Save the configuration
Switch# write memory
```

#### 8. Save Your Configuration

Once you've configured the modules and ports, be sure to save your configuration.

Use commands in the CLI (Command Line Interface) if you're using a model that supports CLI commands.

For example:


```
bash
                                                                           Copy code
Switch> enable
Switch# configure terminal
Switch(config)# interface range fa0/1 - 24
Switch(config-if-range)# description Connected to LAN
Switch(config-if-range)# no shutdown
Switch(config-if-range)# exit
Switch(config)# vlan 10
Switch(config-vlan)# name Sales
Switch(config-vlan)# exit
Switch(config)# interface vlan 10
Switch(config-if)# ip address 192.168.10.1 255.255.255.0
Switch(config-if)# no shutdown
Switch(config-if)# exit
Switch# write memory
```


**9. Test Your Configuration** • Use the simulation mode to test the

network configuration.

• Add devices (PCs, routers, etc.) and connect them to the switch to ensure that everything is working as expected.

Output:





```
Switch0
                                                                                            X
           Config CLI Attributes
 Physical
                                        IOS Command Line Interface
  ^C
  line con 0
  password India@123
  login
  line vty 0 4
  login
line vty 5 15
  login
  1
  end
  SW1#
  SWl#copy run startup-config
  Destination filename [startup-config]?
  Building configuration...
  [OK]
  SW1#
                                                                                            Paste
                                                                                Сору
□ Тор
```

#### Result:

Switch with Network Modules using Cisco Packet Tracer is Customized.

