



SUREN NETWORK
PLAY WITH TECHNOLOGIES

Server & Services

Step 1 : Assign ip address for router interface

```
ROUTER#show ip interface brief
```

Interface	IP-Address	OK?	Method	Status
ocol				
Ethernet0/0	172.16.0.1	YES	manual	up
Ethernet0/1	8.0.0.1	YES	manual	up
Ethernet0/2	50.0.0.1	YES	manual	up

Step 2 : Assign ip address for client pc

☐ Obtain an IP address automatically

☒ Use the following IP address:

IP address: 50 . 0 . 0 . 10

Subnet mask: 255 . 0 . 0 . 0

Default gateway: 50 . 0 . 0 . 1

Step 3 : Assign ip address for tty linux server


Username : root
Password : password

Edit ifcfg-eth0 file using vi editor

vi /etc/sysconfig/network-scripts/ifcfg-eth0

Press  button for insert

```
QEMU (Linux-1)
```



```
ENABLE=yes  
NAME=Ethernet  
IPADDRESS=172.16.0.10  
CIDRLEN=16  
NETWORK=172.16.0.0  
NETMASK=255.255.0.0  
GATEWAY=172.16.0.1  
BROADCAST=172.16.255.255  
DHCP=no  
~
```

Save this configuration

Esc :wq

Service network restart (To restart nic)

Step 4 : Edit html page using vi editor

```
vi /home/thttpd/index.html
```

Step 5 : Assign ip address for windows server

☐ Obtain an IP address automatically

☒ Use the following IP address:

IP address:	172 . 16 . 0 . 20
Subnet mask:	255 . 255 . 0 . 0
Default gateway:	172 . 16 . 0 . 1

Step 6 : Install IIS service in windows server



- 1 Configure this local server
- 2 Add roles and features
- 3 Add other servers to manage

Add Roles and Features Wizard

Before you begin

DESTINATION SERVER
serve2016

This wizard helps you install roles, role services, or features. You determine which roles, role services, or features to install based on the computing needs of your organization, such as sharing documents, or hosting a website.

To remove roles, role services, or features:
Start the Remove Roles and Features Wizard

Before you continue, verify that the following tasks have been completed:




- The Administrator account has a strong password
- Network settings, such as their IP addresses, are configured
- The most current security updates from Windows Update are installed




If you must verify that any of the preceding prerequisites have been completed, close the wizard, complete the steps, and then run the wizard again.




To continue, click Next.


☐ Skip this page by default

< Previous **Next >** Install Cancel











Once installed services default html page will be created on c:\inetpub\wwwroot\iisstart.html

Step 7 : Access linux webserver from windows pc



Step 8 : Access windows webserver from windows pc




Step 9 : Assign ip in DNS server

☐ Obtain an IP address automatically



☒ Use the following IP address:




IP address:	8 . 8 . 8 . 8
Subnet mask:	255 . 0 . 0 . 0
Default gateway:	8 . 0 . 0 . 1

Step 10 : Install dns service from server manager



Step 10 : Once installed dns service go to tools and open dns and create record for linux webserver





New Zone Wizard

Zone File

You can create a new zone file or use a file copied from another DNS server.

Do you want to create a new zone file or use an existing file that you have copied from another DNS server?

☒ Create a new file with this file name:

com.dns

☐ Use this existing file:

To use this existing file, ensure that it has been copied to the folder %SystemRoot%\system32\dns on this server, and then click Next.

< Back Next > Cancel

New Zone Wizard

Dynamic Update

You can specify that this DNS zone accepts secure, nonsecure, or no dynamic updates.

Dynamic updates enable DNS client computers to register and dynamically update their resource records with a DNS server whenever changes occur.

Select the type of dynamic updates you want to allow:

☐ Allow only secure dynamic updates (recommended for Active Directory)
This option is available only for Active Directory-integrated zones.

☐ Allow both nonsecure and secure dynamic updates
Dynamic updates of resource records are accepted from any client.
 This option is a significant security vulnerability because updates can be accepted from untrusted sources.

☒ Do not allow dynamic updates
Dynamic updates of resource records are not accepted by this zone. You must update these records manually.

< Back Next > Cancel

New Zone Wizard

Completing the New Zone Wizard





You have successfully completed the New Zone Wizard. You specified the following settings:

Name: com
Type: Standard Primary
Lookup type: Forward
File name: com.dns


Note: You should now add records to the zone or ensure that records are updated dynamically. You can then verify name resolution using nslookup.

To close this wizard and create the new zone, click Finish.

< Back Finish Cancel



Step 11: Create dns record for windows webserver



New Host

Name (uses parent domain name if blank):
www


Fully qualified domain name (FQDN):
www.netflix.com.

IP address:
172.16.0.20

☐ Create associated pointer (PTR) record

Add Host Cancel

Step 12: Set preferred dns server ip in client device




☐ Obtain DNS server address automatically

☒ Use the following DNS server addresses:

Preferred DNS server: 8 . 8 . 8 . 8

Alternate DNS server: . . .

Step 13: Access webserver-1 using domain name



Welcome to apache webserver

Step 14: Access webserver-2 using domain name

