


Admin Manual Odoo Module trmnl

1. Start Odoo in the Docker Container


To start the Docker container correctly, use the commands or make commands listed in the README. These are explained in the development.md file located in the docs folder.

Then open the following localhost address from the README: <http://localhost:8069>

When registering for Odoo, use admin as username and password. After that, Odoo should start correctly and the overview page with the most popular apps will open.



In the search bar, search for the module trmnl.



Select the module and click Install. When installing the module, all additional Odoo apps and Odoo modules that trmnl depends on will also be installed automatically.

2. Setup TRMNL Display


To register a TRMNL display for the first time, switch it on using the button on the back of the device.

Then connect your laptop or mobile phone to the TRMNL Wi-Fi network. After connecting to the Wi-Fi, a website will automatically open.

Click on Advanced, then configure a custom API server. The address should be entered in the following format: http://PERSONAL-IP:8069

Afterwards, return to the Wi-Fi menu. Select your preferred Wi-Fi network and connect using the corresponding password.

The device is now registered and should appear in the device overview in Odoo.



3. Configure the Display on the TRMNL Device

Afterwards, you can create a new profile under the Profiles menu in your Odoo overview. Under 1. “Name” enter any name you want for the profile. Under 2. “Device” select one of the registered devices. Under 3. “Odoo Model” define which model should be displayed. Please note that you can only select models from modules that are already installed in Odoo. After selecting the model, default configurations for the remaining settings will automatically be created. These can be adjusted if needed. Once a model is selected a new button 4. “Render Preview” will appear, clicking it will render a preview of the profile, showing how the image will appear on the TRMNL display. Use the 5. “Save Manually” button to save the profile.

The image displays two screenshots of the TRMNL Profiles configuration interface, illustrating the steps to create and preview a profile.

Top Screenshot: New Profile Form

- Navigation:** TRMNL, Devices, Profiles, Display Policy. User: My Company.
- Buttons:** New, Profiles, New, Settings, Lock, Close.
- Form Fields:**
 - IDENTITY:**
 - Name:** (1) Input field.
 - Device:** (2) Dropdown menu.
 - Active:** Toggle switch.
 - DATA SOURCE:** (3)
 - Odoo Model:** ? Dropdown menu.
 - DEVICE DELIVERY STATUS:**
 - Device Last Polled
 - Next Expected Poll
 - Device Refresh Rate ? 0
- Annotation 5:** Points to the 'New' button in the top right corner.

Bottom Screenshot: Render Preview

- Navigation:** TRMNL, Devices, Profiles, Display Policy. User: My Company.
- Breadcrumbs:** New / ExampleProfile / ExampleProfile.
- Buttons:** New, Settings, Lock, Close, 1/1, Previous, Next.
- Form Fields:**
 - Render Preview:** (4) Button.
 - IDENTITY:**
 - Name:** ExampleProfile
 - Device:** TRMNL-9F2AC8
 - Active:** Toggle switch.
 - DATA SOURCE:**
 - Odoo Model:** ? TRMNL Profile
 - View Type:** List
 - Users:** ?
 - CONTENT:**