

# Project Configuration Report

## bt-remote-Redesign

### Target Device:

**Target Part:** EFR32BG22C222F352GN32

Boards:

### Target SDK

Gecko SDK Suite v4.4.6: Amazon 202012.00, Bluetooth 7.3.0, Bluetooth Mesh 6.1.4, EmberZNet 7.5.0.0, Flex 3.7.6.0, MCU 6.6.6.0, Micrium OS Kernel 5.14.00, OpenThread 2.4.6.0 (GitHub-bdb394eb3), Platform 4.4.6.0, USB 1.2.3.0, Wi-SUN 1.10.4.0, Z-Wave SDK 7.21.6.0  
SDK Version: 4.4.6

### Project Generators

- Simplicity IDE Project

### Installed Software Components:

- Application

- *Utility*

- Assert**

- Configurable: true

- Configs: app\_assert\_config.h

- Button Press**

- Sources: app\_button\_press.c

- Configurable: true

- Configs: app\_button\_press\_config.h

- Log**

- Sources: app\_log.c

- Configurable: true

- Configs: app\_log\_config.h

- Bluetooth

- *Application*

- Firmware Update

- In-Place OTA DFU**

- Sources: sl\_bt\_in\_place\_ota\_dfu.c

- Configurable: true

- Configs: in\_place\_ota\_dfu.xml, sl\_bt\_in\_place\_ota\_dfu\_config.h

- GATT Services

**Device Information GATT Service**

Sources: sl\_gatt\_service\_device\_information.c

Configurable: false

**Static GATT Database and Configuration**

Configurable: true

Configs: gatt\_configuration.btconf

- Miscellaneous

**BLE Post Build**

Configurable: false

- *Bluetooth Host (Stack)*

**Bluetooth Core**

Sources: sl\_bt\_stack\_init.c

Configurable: true

Configs: sl\_bluetooth\_config.h

- Features with Commands and Events

**GATT Client**

Configurable: false

**GATT Server**

Configurable: false

**Security Manager**

Configurable: false

**System**

Configurable: false

- *Bluetooth LE Controller (Link Layer)*

- Additional Features

**LE Power Control**

Sources: sl\_bt\_power\_control\_init.c

Configurable: true

Configs: sl\_bt\_power\_control\_config.h

- Features with Commands and Events

**Connection**

Configurable: true

Configs: sl\_bluetooth\_connection\_config.h

**Legacy Advertising**

Configurable: false

**Scanner for legacy advertisements**

Configurable: false

- Platform

- Board

- Board Control**

- Sources: sl\_board\_control\_gpio.c, sl\_board\_control\_stub.c, sl\_board\_init.c

- Configurable: true

- Configs: sl\_board\_control\_config.h

- Board Drivers

- Configuration Over SWO**

- Sources: sl\_cos.c

- Configurable: false

- MX25 Flash Shutdown with usart**

- Sources: sl\_mx25\_flash\_shutdown.c

- Configurable: true

- Configs: sl\_mx25\_flash\_shutdown\_usart\_config.h

- Bootloader

- Bootloader Application Interface**

- Sources: btl\_interface\_ns.c, btl\_interface\_storage.c, btl\_interface.c, btl\_interface\_nsc.c

- Configurable: true

- Configs: btl\_interface\_cfg\_s2c4.h, btl\_interface\_cfg.h, btl\_interface\_cfg\_s2c1.h,  
btl\_interface\_cfg\_s2c2.h, btl\_interface\_cfg\_s2c3.h

- Device

- EFR32BG22

- EFR32BG22C222F352GN32**

- Sources: system\_efr32bg22.c, startup\_efr32bg22.c

- Configurable: true

- Configs: device.yaml

- Driver

- Button

- Simple Button**

- Configurable: true

- Configs: sl\_simple\_button\_btn0\_config.h, sl\_simple\_button\_btn2\_config.h,  
sl\_simple\_button\_btn1\_config.h

- Debug SWO

- SWO Debug**

- Sources: sl\_debug\_swo.c

- Configurable: true

- Configs: sl\_debug\_swo\_config.h

- LED

- Simple LED**

- Configurable: true

- Configs: sl\_simple\_led\_led0\_config.h

- Security

- Memory Protection Unit

- Simple MPU**

- Sources: sl\_mpu.c

- Configurable: false

- Utilities

- Component Catalog**

- Configurable: false

- Services

- IO Stream

- IO Stream: EUSART Core**

- Sources: sl\_iostream\_eusart.c

- Configurable: false

- Driver

- IO Stream: EUSART**

- Configurable: true

- Configs: sl\_iostream\_eusart\_vcom\_config.h

## Pins:

| Pin # | Pin Name | Function   | Custom Pin Name | Software Component       |
|-------|----------|------------|-----------------|--------------------------|
| 17    | PA00     | GPIO mode  | led             | Simple LED (led0)        |
| 18    | PA01     | GPIO_SWCLK |                 | SWO Debug                |
| 19    | PA02     | GPIO_SWDIO |                 | SWO Debug                |
| 20    | PA03     | GPIO_SWV   |                 | SWO Debug                |
| 21    | PA04     | GPIO mode  | button2         | Simple Button (btn2)     |
| 22    | PA05     | GPIO mode  | button1         | Simple Button (btn1)     |
| 23    | PA06     | GPIO mode  | button0         | Simple Button (btn0)     |
| 16    | PB00     |            |                 |                          |
| 15    | PB01     |            |                 |                          |
| 14    | PB02     |            |                 |                          |
| 1     | PC00     |            |                 |                          |
| 2     | PC01     |            |                 |                          |
| 3     | PC02     | EUSART0_TX |                 | IO Stream: EUSART (vcom) |
| 4     | PC03     | EUSART0_RX |                 | IO Stream: EUSART (vcom) |
| 5     | PC04     |            |                 |                          |
| 6     | PC05     |            |                 |                          |

|    |      |  |  |  |
|----|------|--|--|--|
| 32 | PD00 |  |  |  |
| 31 | PD01 |  |  |  |

## Peripherals:

| Peripheral           | Software Component       | Custom Peripheral Name |
|----------------------|--------------------------|------------------------|
| CMU                  |                          |                        |
| EUART0               | IO Stream: EUSART (vcom) |                        |
| GPIO                 | SWO Debug                |                        |
| I2C0                 |                          |                        |
| I2C1                 |                          |                        |
| IADC0                |                          |                        |
| LETIMER0             |                          |                        |
| LFXO                 |                          |                        |
| MODEM                |                          |                        |
| PDM                  |                          |                        |
| PRS Channel ASYNCH0  |                          |                        |
| PRS Channel ASYNCH1  |                          |                        |
| PRS Channel ASYNCH10 |                          |                        |
| PRS Channel ASYNCH11 |                          |                        |
| PRS Channel ASYNCH2  |                          |                        |
| PRS Channel ASYNCH3  |                          |                        |
| PRS Channel ASYNCH4  |                          |                        |
| PRS Channel ASYNCH5  |                          |                        |
| PRS Channel ASYNCH6  |                          |                        |
| PRS Channel ASYNCH7  |                          |                        |
| PRS Channel ASYNCH8  |                          |                        |
| PRS Channel ASYNCH9  |                          |                        |
| PRS Channel SYNCH0   |                          |                        |
| PRS Channel SYNCH1   |                          |                        |
| PRS Channel SYNCH2   |                          |                        |
| PRS Channel SYNCH3   |                          |                        |
| PTI                  |                          |                        |
| TIMER0               |                          |                        |
| TIMER1               |                          |                        |
| TIMER2               |                          |                        |
| TIMER3               |                          |                        |
| TIMER4               |                          |                        |
| USART0               |                          |                        |
| USART1               |                          |                        |