



Post migration printer mapping

User guide

OVERVIEW.....	3
MAPPING MIGRATED PRINTER.....	4
Step 1: Find Your New Printer Name	4
Step 2: Open the Fresenius Print Server	4
Step 3: Locate and Install Your printer	5
PRINTER MAPPING VERIFICATION	6
PRINT A TEST PAGE	7
SET AS DEFAULT PRINTER (OPTIONAL).....	8
ADDITIONAL SUPPORT	9

OVERVIEW

As part of your migration to the **Fresenius IT environment**, previously configured printers may no longer appear automatically on your device and need to be mapped again.

This guide explains how to reconnect to your required Fresenius printers using the official print server and confirms how to verify that the printer has been installed correctly. The guide applies to all users who need access to shared/network printers. The printers are hosted on the Fresenius print server and can be added directly from Windows.

Before you begin, please ensure that:

- You are connected to the Fresenius corporate network
- You know the name of the printer you would like to add

NOTE:

Post migration, your printer name has changed. New printer name can be found on your printer label as per below example:

PRINTER IDENTIFICATION		myIT	
DEVICE INFORMATION			
HOST NAME / GLOBAL PRINTER NAME			
DEANS1RNF			
Naming: 3-digit country + 3-digit city + 4-digit SAP queue, e.g. D000R000.			
LOCATION INFO		PRINTER MODEL	
ANSBACH		BIZHUB C3300i	
SERIAL NUMBER		IP ADDRESS	
{{SERIAL_NUMBER}}		10.184.25.212	
If you need help or support with this printer please contact the Global Service Desk below. You can use the QR codes on company phones for quick access:			
FreDi IN MICROSOFT TEAMS		Support Portal IN WEB BROWSER	
			
		Support Phone {{Enter local number here}}	
Fresenius			

MAPPING MIGRATED PRINTER

Step 1: Find Your New Printer Name

Before adding your printer, please identify its new Fresenius printer name.

A printer identification label has been placed on each migrated printer. The printer name is displayed in the **"HOST NAME / GLOBAL PRINTER NAME"** field and will be required during the printer mapping process.

Example:


PRINTER IDENTIFICATION	
myIT	
DEVICE INFORMATION	
HOST NAME / GLOBAL PRINTER NAME	
DEANS1RNF	
Naming: 2 digit country + 3 digit city + 4 digit SAT system, e.g. 0000100001	
LOCATION INFO	PRINTER MODEL
ANSBACH	BIZHUB C3900i
SERIAL NUMBER	IP ADDRESS

In the example above, the printer name is: **DEANS1RNF**


Make a note of your printer name before proceeding to the next step.

Step 2: Open the Fresenius Print Server

1. Press **Windows + R** on your keyboard to open the **Run** window.



2. Enter the following address:
[\\PFDTFHSAP1001.ads.fresenius.com](https://PFDTFHSAP1001.ads.fresenius.com)




3. Click **OK** or press **Enter**.

A new window will open displaying all printers available on the Fresenius print server.

Step 3: Locate and Install Your printer

1. In the printer list, locate the printer name identified in **Step 1**.



2. Double-click the printer.

3. Windows will automatically install the printer and any required drivers.


4. Wait until the installation is complete.

You will see the confirmation message: "Printer successfully added."


PRINTER MAPPING VERIFICATION

Once the installation is complete, verify that the printer is available on your device.

1. Go to Printers & scanners in your windows search window.



1. Review the list of available printers.
2. Confirm that your printer name appears in the list.




If the printer is listed, the mapping has been completed successfully.


PRINT A TEST PAGE

To confirm that the printer is working correctly, follow below steps:


1. Once again, go to Printers & scanners in your windows search window.




2. Select your newly added printer.



3. Click Printer properties.



4. Select Print Test Page.




A test page should be printed successfully.

SET AS DEFAULT PRINTER (OPTIONAL)

If this is your primary printer, you may want to set it as your default printer.

1. Open **Settings** → **Bluetooth & devices** → **Printers & scanners**.

2. Select your printer.



3. Choose **More devices and printers settings**.

Bluetooth & devices > Printers & scanners > **DENS1RNF**



Remove

DENS1RNF settings Scanner settings

Open print queue



Print test page



Printer properties



Printing preferences

Orientation, page order, pages per sheet, borders, paper source



Additional printer settings

Rename your printer, pause printing



Hardware properties



More devices and printers settings




More information

Scanners not appearing



4. New pop-up window will appear
5. Select your desired default printer.
6. Right click on printer icon
7. Choose **Set as default printer**



Your print jobs will now be sent to this printer by default.

ADDITIONAL SUPPORT

If you experience any issues while reconnecting or using your printer, please contact the **Fresenius Service Desk**:

- **Phone:** +49 (0)6172 608-1111 (DE)
- **Email:** GlobalServiceDesk@fresenius.com
- **Service Portal:** <https://fnc.service-now.com/sp>