

Stash

A small private safe for passwords, PINs and other secrets

⚠ FOR UNDERSTANDING PURPOSES ONLY — NOT FOR COMMERCIAL OR TEACHING USE

Prasanaa Kartick T — Personal App Project

Flutter / Dart · Android

🔑 Cards

👁 Hidden

🌫 Blurred

🔒 Own lock

1. What It Is

Stash is the app's private secrets keeper — deliberately given a bland name so that neither the footer label nor the screen title gives away what it holds. Each saved item is a small card: a **title** you choose (for example “Net Banking” or “Gmail”) and the **secret content** beneath it.

2. How a Card Behaves

- The content stays **hidden** until you tap the eye icon on that card — and even then it is shown **lightly blurred**, not as plain text.
- Cards are stored with a unique ID, the title, the content and the creation date.
- Even once unlocked, the screen stays **blank until you search** for a card's name — an extra layer of “don't show everything at a glance”.

3. Its Own Lock

Stash can have a lock of its own, independent of the everyday App Lock: a **PIN and a Pattern** set up together in Privacy Settings. If it exists, it must be passed fresh — with no “stays unlocked for a while” grace period — at every sensitive moment:

- opening Stash at all
- switching Edit mode on
- revealing a card's content
- editing a card

No lock, no entry

If no Stash lock has been set up, Stash refuses to open and shows a “Set up a Stash lock to continue” prompt. It never falls back to opening unprotected.

4. How the Stash Lock Works

Feature	Detail
Random challenge	Each check asks for either the PIN or the Pattern, picked like a coin flip — so someone who has only glimpsed one still can't reliably get in
Retrying a typo	A wrong answer keeps the same challenge up so a genuine slip can be retried
Lock-out	After five wrong attempts in a row (PIN and Pattern mistakes count together), Stash locks out for five minutes with a countdown
Shuffled keypad	The PIN pad's digit layout is reshuffled every time it is shown and after a wrong attempt
Biometrics	Optional fingerprint / face unlock as a substitute; a cancelled or failed scan does not count against the five attempts
Forgot Password	Always available, even during a lock-out, because it is a separate check rather than another PIN or Pattern guess
Changing the lock	Requires both the current PIN and the current Pattern

5. Adding a Card

A simple form: **Card Title** and **Content**, with the content hidden by default and an eye button to peek while typing. Both are required. A short note explains that the content stays hidden and blurred on the card. Saving plays the “saved” chime and hands the new card back to the Stash screen, which stores it. Editing happens inline on the Stash screen itself.