

Assignment: Reliable UDP Communication in Mininet

NAME: Kaushal kumar ROLL: CSB24069

Objectives:

In this assignment, students will build a UDP client-server application in Mininet and add basic reliability using sequence numbers, ACKs, timeout, and retransmission.

Given Experiment:

Run the final program under the following three Mininet conditions. Run each condition once.

`sudo mn --link tc,bw=5,delay=30ms,loss=0`

`sudo mn --link tc,bw=5,delay=30ms,loss=5`

`sudo mn --link tc,bw=5,delay=30ms,loss=10:`

Short Answer these:

1. Why is ACK needed?
 2. Why is timeout needed?
 3. Why can duplicate messages occur?
 4. What happens when packet loss increases?
 5. How is this method similar to TCP?
 6. How is it different from TCP?
-

Experiment 1: Loss = 0%

Roll	Name	loss_percent	Timeout	total_message	total_packet_sent	total_retransmissions	transfer_time_seconds	Status
CSB24069	KAUSHAL	00	1.5	10	10	0	1.3811	SUCCESS

Experiment 2: Loss = 5%

Roll	Name	loss_percent	Timeout	total_message	total_packet_sent	total_retransmissions	transfer_time_seconds	Status
CSB24069	KAUSHAL	5	1.5	10	13	3	5.8986	SUCCESS

Experiment 3 :Loss=10%

Roll	Name	loss_percent	Timeout	total_message	total_packet_sent	total_retransmissions	transfer_time_seconds	Status
CSB24069	KAUSHAL	10	1.5	10	12	2	4.4571	SUCCESS

Q1. Why is ACK needed?

Ans: ACK (Acknowledgement) is needed to confirm that the receiver has successfully received a packet. In UDP, packets can be lost because it does not provide built-in reliability. The sender waits for an ACK after sending each packet. If the ACK is not received within the timeout period, the sender assumes the packet or ACK was lost and retransmits the packet. Therefore, ACK helps achieve reliable communication in the Stop-and-Wait protocol.

Q2. Why is timeout needed?

Timeout is needed because the sender cannot wait forever for an ACK from the receiver. If a packet or its ACK is lost, the timeout allows the sender to detect the loss and retransmit the same packet. This helps ensure that all messages are delivered successfully. In the Stop-and-Wait protocol, timeout plays an important role in providing reliability over UDP.

Q3. Why can duplicate messages occur?

Duplicate messages can occur when the sender does not receive an ACK within the timeout period and retransmits the same packet. Sometimes the original packet was received successfully, but the ACK sent by the receiver was lost. The receiver then receives the same packet again and identifies it as a duplicate using the sequence number. This is a common situation in Stop-and-Wait reliable communication over UDP.

Q4. What happens when packet loss increases?

When packet loss increases, more data packets or ACK packets may be lost during transmission. This causes the sender to wait for the timeout and retransmit the lost packets. As a result, the number of retransmissions and the total transfer time

increase. Higher packet loss reduces communication efficiency and may lead to more duplicate packets at the receiver.

Q5. How is this method similar to TCP?

This Stop-and-Wait method is similar to TCP because both provide reliable communication by using acknowledgements (ACKs), sequence numbers, and retransmissions. They ensure that lost packets are sent again and that data reaches the receiver correctly. Both methods also use mechanisms to detect duplicate packets and maintain reliable data transfer over an unreliable network.

Q6. How is it different from TCP?

This method is different from TCP because it implements only basic reliability using sequence numbers, ACKs, timeouts, and retransmissions. TCP provides additional features such as connection establishment, flow control, congestion control, and automatic error handling. TCP also manages data transfer efficiently, whereas this Stop-and-Wait method sends only one packet at a time and is slower. Therefore, it