

Get LCAI — swap Ethereum for native LCAI

Live app: <https://orcavault.win/get-lcai/>

A public, **non-custodial** page: connect a wallet with **ETH on Ethereum**, pick an amount, get a live Uniswap **V3** quote, then swap **ETH → LCAI ERC-20** and bridge to **native LCAI on Lightchain (domain 9200)** via the **official** Hyperlane warp. Native LCAI is delivered to **your own Lightchain wallet** (same address). No backend, no API keys, no app unlock.

Read first. You sign every step — we never hold funds. Native LCAI is **not instant**: after Ethereum confirms, the official Lightchain Hyperlane relayer delivers. **LCAI has no Uniswap V2 pool** — quotes and swaps use **V3 (0.3% LCAI/WETH)**. This is **not** Circle and **not** a CEX.

Two different ETH rails. OrcaVault Pay with Ethereum sends native LCAI to the app relay to unlock uploads. **Get LCAI** sends native LCAI to you. The self-hosted Base USDC warp is a third, separate route.

What you do in the app

1. Open <https://orcavault.win/get-lcai/>
2. Connect MetaMask or Trust (must use **Ethereum mainnet**).
3. Enter ETH or tap a preset. The quote is live from Uniswap V3.
4. Approve the swap, approve LCAI spend if asked, approve the bridge.
5. Wait, then add/switch to **Lightchain AI (chain 9200)** to see native LCAI (details below).

You sign every step. The page never holds funds.

Seeing your balance

Native LCAI lands on **Lightchain**, not Ethereum, so it will not appear in the wallet's default Ethereum view.

1. Add a custom network:
 - **Network name:** Lightchain AI
 - **RPC URL:** <https://rpc.mainnet.lightchain.ai>
 - **Chain ID:** 9200
 - **Currency symbol:** LCAI
 - **Block explorer:** <https://lightscan.app>
2. Switch to **Lightchain AI**. LCAI is the native coin (main balance). Some wallets need LCAI toggled under **Manage crypto**.
3. Delivery is not instant: the official Hyperlane relayer mints native LCAI a few minutes after the bridge tx confirms.

Source of truth: some wallet indexers (e.g. Trust Wallet) lag or do not fully cover smaller networks, so the UI may still show 0. Search your address at **lightscan.app** — if it shows there, the LCAI is in the wallet regardless of the app display.

Public contracts (Ethereum unless noted)

Role	Address
LCAI ERC-20	0x9cA8530CA349c966Fe9ef903Df17a75B8A778927
WETH9	0xC02aaA39b223FE8D0A0e5C4F27eAD9083C756Cc2

Uniswap V3 SwapRouter	0xE592427A0AEce92De3Edee1F18E0157C05861564
Uniswap V3 Quoter	0xb27308f9F90D607463bb33eA1BeBb41C27CE5AB6
LCAI/WETH V3 pool (0.3%)	0x0d047a370611437a1b8e6c2a95ea36f69fdda3be
Warp (Ethereum collateral)	0x01f80bb8e78e79881E8Ec7832fB6C2c59f64e353
Warp (Lightchain native mint)	0xEc7096A3116EE769457C939617375Ec1785AA6f1
Lightchain domain	9200

Same official stack as Pay-with-Ethereum; only the **recipient** changes (your address vs an app relay).

Safety

1. Official warp only — do not send LCAI ERC-20 to a random router.
2. Keep enough ETH for the swap, Uniswap fee, and Hyperlane `quoteGasPayment` .
3. Slippage applies. Not instant. Not Circle.
4. Source lives at `get-lcai/` in the OrcaVault repo (relative `./eth-pay.js`). No extra domain.

App: orcavault.win/get-lcai/ · Related: [Pay with Ethereum \(unlock\) PDF](#) · [Hyperlane USDC warp \(self-hosted\)](#) · [bridge.lightchain.ai](#). Public contracts only — no ops keys or test wallets.