HOME YOUTUBE TWITTER

SUBSCRIBE

Q

SOL Standard

Insert the Date Values in SQL

7 months ago • by John Otieno

Accurate time and date are invaluable tools when it comes to databases. One of the most common tasks when dealing with databases and time is inserting a current date value into the database.

SQL comes packed with lots of tools, data types, and functions for manipulating, retrieving, and using the date and time information including the current date and time.

In this tutorial, we will learn about the date data type and how to insert a date value into an SQL table.

SQL DATE Type

The DATE data type allows you to store the date values. The following demonstrates how to define a column with the DATE data type:

column name DATE

One advantage of the DATE data type is that it is available in all database engines. This means that a date column is supported in MySQL, PostgreSQL, SQL Server, and Oracle. This makes it versatile and quite easy to remember.

Once we created a column with DATE type, we can insert a date value either using a date literal or a date-related function.

For example, to insert a date literal value, we can use the format as follows:

'YYYY-MM-DD'

Where:

- 1. YYYY represents the year with four digits (e.g., 2024)
- 2. MM represents the month with two digits (e.g., 01)
- 3. DD represents the day with two digits (e.g., 01)

NOTE: The valid range for the DATE values is 1000-01-01 to 999-12-31.

Create a Table

The following shows a basic create table statement that contains a date column. This helps us to demonstrate how to use the function:

```
create table t(
id int auto_increment primary Key NOT NULL,
date_var DATE NOT NULL
);
```

This should create a table called "t" with the "ID" and "date_var" columns.

Insert a Date

As mentioned, we can insert a date value by either using a date literal or using the daterelated functions.

The following example shows how to use a date literal and the "current_date" function to insert the current date into the table:

```
INSERT
INTO
t(date_var)
VALUES ('2024-12-2'),
(CURRENT_DATE());
```

The given example should insert the provided string literal and the current date from the function.

The resulting table is as follows:

```
id|date_var |
--+----+
1|2024-12-02|
2|2024-01-21|
```

Conclusion

This tutorial covers the date data type in SQL. It is one of the most fundamental type for storing the date values within the database. We also learned how to insert the date values as string literals or using the date-related functions.

ABOUT THE AUTHOR

John Otieno



My name is John and am a fellow geek like you. I am passionate about all things computers from Hardware, Operating systems to Programming. My dream is to share my knowledge with the world and help out fellow geeks. Follow my content by subscribing to LinuxHint mailing list

View all posts

RELATED LINUX HINT POSTS
Add a Column to the Table in SQL
Compare Two Tables in SQL
Combine Two Columns in SQL
SQL Having Clause
SQL Subtract
SQL Select All Except
SQL Outer Join

Linux Hint LLC, editor@linuxhint.com 1210 Kelly Park Circle, Morgan Hill, CA 95037

Privacy Policy and Terms of Use