```
from google.colab import files
uploaded = files.upload()
```

```
<IPython.core.display.HTML object>
```

```
Saving wav2vec2_finetuned.zip to wav2vec2_finetuned.zip
```

```
!unzip wav2vec2_finetuned.zip
```

```
Archive:  wav2vec2_finetuned.zip
   creating: wav2vec2_finetuned/
  inflating: wav2vec2_finetuned/model.safetensors
  inflating: wav2vec2_finetuned/config.json
  inflating: wav2vec2_finetuned/processor_config.json
  inflating: wav2vec2_finetuned/tokenizer_config.json
  inflating: wav2vec2_finetuned/vocab.json
  inflating: wav2vec2_finetuned/training_args.bin
```

```
model_path = "/content/wav2vec2_finetuned"
```

```
from google.colab import files
uploaded = files.upload()
audio_path = list(uploaded.keys())[0]
```

```
<IPython.core.display.HTML object>
```

```
Saving sample_audio.wav to sample_audio.wav
```

```
from IPython.display import Audio, display
# !ffmpeg -i "$audio_path" -ar 16000 -ac 1 converted.wav -y

display(Audio(audio_path))
```

```
<IPython.lib.display.Audio object>
```

```
!pip install -q openai-whisper jiwer
```

```
━━━━━━━━━━━━━━━━━━━━━━━━━━━━━━━━━━━━━━━━ 0.0/803.2 kB ? eta -:--:--
━━━━ ━━━━━━━━━━━━━━━━━━━━━━━━━━━━━━━━━━━ 92.2/803.2 kB 2.5 MB/s eta
0:00:01 ━━━━━━━━━━━━ ━━━━━━━━━━━━━━━━━━━━━━━━━━ 266.2/803.2 kB 4.0
MB/s eta 0:00:01 ━━━━━━━━━━━━━━━━━━━━━━━━━━━━━━━━ ━━━━━━ 665.6/803.2
kB 6.4 MB/s eta 0:00:01 ━━━━━━━━━━━━━━━━━━━━━━━━━━━━━━━━━━━━━━━
803.2/803.2 kB 6.6 MB/s eta 0:00:00
ents to build wheel ... etadata (pyproject.toml) ...
━━━━━━━━━━━━━━━━━━━━━━━━━━━━━━━━━━━━━━━━ 3.1/3.1 MB 46.7 MB/s eta
0:00:00
━━━━━━━━━━━━━━━━━━━━━━━━━━━━━━━━━━━━━━━━ 197.7/197.7 MB 6.3 MB/s eta
0:00:00
l) ...
```

```
import whisper
from jiwer import wer
```

```python
whisper_model = whisper.load_model("base")  # or your saved/fine-tuned model
result = whisper_model.transcribe(audio_path)
print("Whisper Transcript:")
pred_text =  result["text"].upper()

print(pred_text)
```

```
/usr/local/lib/python3.12/dist-packages/whisper/transcribe.py:132: UserWarning: FP16 is not supported on CPU; using FP32 instead
  warnings.warn("FP16 is not supported on CPU; using FP32 instead")

Whisper Transcript:
 MR. QUILTER IS THE APOSTLE OF THE MIDDLE CLASSES, AND WE ARE GLAD TO WELCOME HIS GOSPEL.
```

```python
from transformers import pipeline

asr_pipe = pipeline(
    "automatic-speech-recognition",
    model=model_path
)

wav2vec_result = asr_pipe(audio_path)

print("Wav2Vec2/Transformer Transcript:")
print(wav2vec_result["text"])
```

{"model_id":"d84f9e2b643b452fb83ee225ef5ccf46","version_major":2,"version_minor":0}

```
Wav2Vec2/Transformer Transcript:
MISTER QUILTER IS THE APOSTLE OF THE MIDDLE CLASSES AND WE ARE GLAD TO WELCOME HIS GOSPEL
```

```python
print("===== WHISPER =====")
print(pred_text)

print("\n===== WAV2VEC2 / TRANSFORMER =====")
wav2vec_pred = wav2vec_result["text"]
print(wav2vec_pred)
```

```
===== WHISPER =====
 MR. QUILTER IS THE APOSTLE OF THE MIDDLE CLASSES, AND WE ARE GLAD TO WELCOME HIS GOSPEL.

===== WAV2VEC2 / TRANSFORMER =====
MISTER QUILTER IS THE APOSTLE OF THE MIDDLE CLASSES AND WE ARE GLAD TO WELCOME HIS GOSPEL
```

to calculate the wer of this please input the actual script here

```
actual_text = "MISTER QUILTER IS THE APOSTLE OF THE MIDDLE CLASSES AND WE ARE GLAD TO WELCOME HIS GOSPEL"

whisper_wer = wer(actual_text, pred_text)
wav2vec_wer = wer(actual_text, wav2vec_pred)



print("Whisper WER %:", whisper_wer * 100)
print("Wav2Vec2 WER %:", wav2vec_wer * 100)
```

```
Whisper WER %: 17.647058823529413
Wav2Vec2 WER %: 0.0
```