

Email Signatures — Installation Guide

One file per person. The logo is embedded — nothing else to upload.

THE ONE STEP EVERYONE DOES FIRST

1. Open your own signature file (EDM-Email-Signature-YourName.html). It opens in your browser and shows the finished signature.
2. Select the whole signature — logo down to the UAE · Ireland · UK · Australia line — and copy it. Phone: press and hold, Select All, Copy. Laptop: Ctrl+A then Ctrl+C (Cmd on Mac).

Everything below is just where to paste it. The recommended route on any device is Outlook on the web, because a signature saved there follows your account onto every device automatically.

IPHONE

1. In Safari, go to outlook.office.com and sign in with your EDM email.
2. Tap the gear (Settings) > Account > Signatures.
3. Press and hold in the signature box and Paste. Name it EDM.
4. Tick it as default for New Messages and for Replies/Forwards, then Save.

The Outlook iPhone app then uses this automatically on most business accounts. If the app still shows its own plain-text signature: Outlook app > Settings > your account > Signature > paste the same copied signature there.

ANDROID

1. In Chrome, go to outlook.office.com, sign in, and follow the same four steps as iPhone (Settings > Account > Signatures > paste > default > Save).
2. If the Outlook Android app shows its own signature: Outlook app > Settings > your account > Signature > paste. If Android paste loses the logo, set the signature on the web as above — it takes priority for mail sent from the web and syncs on most business accounts.

LAPTOP — WINDOWS

1. Open the signature file in your browser, Ctrl+A, Ctrl+C.
2. Outlook: File > Options > Mail > Signatures > New. Name it EDM.
3. Click into the editing box, Ctrl+V to paste.
4. Set it as default for New Messages and Replies/Forwards, then OK.

LAPTOP — MAC

1. Open the file in Safari or Chrome, Cmd+A, Cmd+C.
2. Outlook: Outlook menu > Settings > Signatures > + to add. Name it EDM, paste, set as default, close.

THE TEST — NOT DONE UNTIL THIS PASSES

Send yourself one email from each device you use. Check three things: the cube logo shows, the name, number and email are yours, and the layout matches the file. If the logo is missing or the layout has collapsed, delete the signature and redo the copy — the usual cause is a partial selection that missed the top of the signature.