LAB EXPERIMENT - 05

Department	AIDS
Course Code / Course Name	ITA1409 - ETHICAL HACKING
Name	B KIRTHANAA
Register Number	192324244

Q5. Execute and Display the Results of uptime, date, and mv Commands in Kali Linux Operating System

AIM

To execute and display the results of the uptime, date, and mv commands in the Kali Linux operating system and understand their basic functions.

PROCEDURE

1. Open the Kali Linux Terminal and navigate to the home directory.
2. Create a sample directory, a directory named Lab_Files, and sample files using the mkdir, touch, and echo commands.
3. Execute the uptime command to display how long the system has been running.
4. Execute the date command to display the current system date and time.
5. Execute the mv command to move a file into a directory and to rename a file, and verify the result using ls.
6. Observe and verify the output of all three commands and understand their functions.
7. Capture screenshots of the terminal showing the execution and output of the commands as evidence.

COMMANDS TO EXECUTE

First, create a sample directory and files:

```
mkdir Sample
cd Sample
echo -e "Line 1: Kali Linux\nLine 2: Operating System\nLine 3: uptime command\nLine 4: date command\nLine 5: mv command" > sample.txt
touch notes.txt
mkdir Lab_Files
```


Then execute:

1. uptime Command

The uptime command is used to display the current time, how long the system has been running, the number of logged-in users, and the system load averages for the last 1, 5, and 15 minutes. The option -p shows the uptime in a human-readable (pretty) format.

```
uptime
uptime -p
```

OUTPUT:




2. date Command

The date command is used to display the current system date and time. A custom format can be given using the + option.

```
date
date +"%d-%m-%Y %H:%M:%S"
```

OUTPUT:




3. mv Command

The mv (move) command is used to move files or directories from one location to another, and also to rename a file or directory.

```
mv sample.txt Lab_Files/
mv notes.txt renamed.txt
```

OUTPUT:



RESULT

The uptime, date, and mv commands were successfully executed in Kali Linux. The uptime command was used to display how long the system has been running, the date command was used to display the current system date and time, and the mv command was used to move and rename files.