



MID Server

Management Instrumentation and **D**iscovery



- Java Application that enables communication and data movement between a ServiceNow instance and external applications, data sources, and services.
- Initiates all communications with Instance.
- Communication log between the instance and the MID Server is recorded in "MID Server ECC Queue"





Requirements - MID Server

Supported OS : (64-bit)

- Windows Server 2012, Windows Server 2016
- Windows Server 2019, Windows Server 2022
- Linux Red Hat 6 and above
- Ubuntu 1404 (Ubuntu 14) and above
- CentOS 7 and above

Non Supported OS : (64-bit)

- CentOS 7, Windows server 2008
- Windows server 2008 R2, Windows 8
- Windows 10



PowerShell requirements : Minimum PowerShell version 3.0 and supports versions up to PowerShell 5.1.

Java version support : Java 11.0.16.1 (comes with MID Server installer package, No configuration needed)

CPU : Minimum quad core processor with a speed of 2+ GHz for single MID Server

Memory : Greater than 1 GB (Mid Server installs with 1 GB of JVM memory)

MID Server - Installation

1 - Using Guided setup - Guided setup provides a sequence of tasks that help you install a MID Server with the proper user account and validate the MID Server.

2 - MID Server manual installation -

- Create the MID Server user account
- Download the installer file
- Install the MID Server on a Linux or Windows host
- Validate the MID Server to ensure that it is trusted to access credentials
- Test connectivity

MID Server - Parameters

config.xml

config.xml stores mid server configuration data.

Required Parameters for config.xml

- **url** - URL to the associated instance
- **mid_sys_id** - MID Server record's unique identifier. should be empty when you initially configure a MID Server
- **name** - Mid Server Name
- **mid.instance.username** - mid server username configured in instance.
- **mid.instance.password** - mid server user's password



MID Server - logs

The MID server logs are kept in the `.\agent\logs` folder. The MID server writes information to two main logs:

- **agent log** - where the MID server specific code writes messages to, info, debug, etc
- **wrapper.log** - where the java service sends logs to. This is also where the MID server upgrade service writes information to.

The MID server logs can be retrieved directly on the instance.

- In mid server record Click on link "Grab MID logs, files and thread dump".
- Related list "Agent Logs" and "Agent Files" will be populated.

MID Server - enable debug mode

mid.log.level is very useful property to be set when debugging and troubleshooting. Steps to add this property in the instance.

- Login to instance
- Go to MID servers >> Servers
- Open the MID server from the list which you want to add Debug mode
- Go to configuration parameter
- Search for property mid.log.level and select it
- Add the value as DEBUG (all in uppercase)
- Save



MID Server - Troubleshooting Links

- **MID Server Down troubleshooting** - https://support.servicenow.com/kb?id=kb_article_view&sysparm_article=KB0661756
- **MID Server Auto Upgrade hanging issues** - https://support.servicenow.com/kb?id=kb_article_view&sysparm_article=KB0813730
- **Enable SSH Debug on a MID server** - https://support.servicenow.com/kb?id=kb_article_view&sysparm_article=KB0727653
- **MID Servers and Certificates** - https://support.servicenow.com/kb?id=kb_article_view&sysparm_article=KB0863673
- **Controlling mid server version and mid server upgrades** - support.servicenow.com/kb?id=kb_article_view&sysparm_article=KB0714102

