MIT WORLD PEACE UNIVERSITY

Computer Networks Second Year B. Tech, Semester 3

CONFIGURATION OF STATIC AND DYNAMIC NAT

PRACTICAL REPORT ASSIGNMENT 6

Prepared By

Krishnaraj Thadesar Cyber Security and Forensics Batch A1, PA 20

November 27, 2022

Contents

1	Aim and Objectives	1
2	Devices 2.1 Devices Used	1 1
3	Cables	1
4	Procedure to Configure the Network	1
5	Commands	1
6	Platform	2
7	Output	3
8	Connection Screenshot	3
9	Conclusion	3

1 Aim and Objectives

Implement Static and Dynamic NAT Configuration with Packet Tracer

2 Devices

2.1 Devices Used

- 1. 1 Switch 2960 with 24 LAN Ports
- 2. 2 Generic PCs
- 3. 2 Routers.
- 4. 1 Server.

3 Cables

- 1. Straight LAN Cable to connect unlike Devices
- 2. Crossover LAN Cable to connect like Devices

4 Procedure to Configure the Network

- 1. Create the Network as shown in the figure below.
- 2. Connect the various components with respective cables.
- 3. Assign IP Addresses to the devices.
- 4. Execute Appropriate commands on the routers.
- 5. Open Web browser on PCs and Laptops and check if they are able to access the server public IP.

5 Commands

FOR ROUTER O

Router>
Router#
Router(config-if)#clock rate 56000
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#interface GigabitEthernet0/0/0
Router(config-if)#ip nat inside
Router(config-if)#exit

Computer Networks Assignment 6

Router(config)#interface Serial0/2/0 Router(config-if)#ip nat outside

Router(config-if)#exit


```
Router(config)#ip nat inside source static 10.0.0.1 213.20.1.1
Router(config)#ip route 0.0.0.0 0.0.0.0 Serial0/2/0
%Default route without gateway, if not a point-to-point interface, may impact performance
Router(config)#
FOR ROUTER 2
Router>enable
Router#
Router(config-if)#clock rate 56000
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#interface GigabitEthernet0/0/0
Router(config-if)#ip nat inside
Router(config-if)#exit
Router(config)#interface Serial0/1/0
Router(config-if)#ip nat outside
Router(config-if)#exit
Router(config)#ip nat inside source static 20.0.0.1 213.20.1.2
Router(config)#ip nat inside source static 20.0.0.2 213.20.1.2
Router(config)#
Router(config)#
Router(config)#interface GigabitEthernet0/0/0
Router(config-if)#
Router(config-if)#exit
Router(config)#interface GigabitEthernet0/0/0
Router(config-if)#
Router(config-if)#exit
Router(config)#ip route 0.0.0.0 0.0.0.0 Serial0/1/0
"Default route without gateway, if not a point-to-point interface, may impact performance
Router(config)#
```

6 Platform


Operating System: Arch Linux x86-64

IDEs or Text Editors Used: Visual Studio Code **Programs Used**: Cisco Packet Tracer v6.0.1

7 Output



8 Connection Screenshot



9 Conclusion

Thus we have successfully configured Static and Dynamic NAT in Cisco Packet Tracer.