
MODUL 7


Nama : Fachrul Rinaldi

NIM : L200170042

Kelas : A



1. Konfigurasi masing masing interface pada tiap Router



IOS Command Line Interface

```
--- System Configuration Dialog ---
Would you like to enter the initial configuration dialog? [yes/no]: no
Press RETURN to get started!
Router>en
Router#config
Configuring from terminal, memory, or network [terminal]?
Enter configuration commands, one per line. End with {\tt CNTL/Z}\,.
Router(config) #int fa 0/0
Router(config-if) #ip address 172.21.20.20 255.255.255.0 Router(config-if) #no shutdown
Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up
Router(config-if) #int se 2/0
Router(config-if) #ip address 172.21.1.2 255.255.255.0
Router(config-if) #no shutdown
Router(config-if)#
%LINK-5-CHANGED: Interface Serial2/0, changed state to up
Router(config-if) #int se 3/0
Router(config-if) #clo
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial2/0, changed state to
Router(config-if) #int se 3/0
Router(config-if) #clock rate 2000000
Router(config-if) #ip address 172.21.3.2 255.255.255.0
Router(config-if) #no shutdown
%LINK-5-CHANGED: Interface Serial3/0, changed state to down
Router(config-if)#
```


Ctrl+F6 to exit CLI focus


IOS Command Line Interface

```
Press RETURN to get started!
Router>en
Router#conf
Configuring from terminal, memory, or network [terminal]?
Enter configuration commands, one per line. End with CNTL/Z.
Router(config) #int fa 0/0
Router(config-if) #ip address 172.21.30.30 255.255.255.0
Router(config-if) #no shutdown
Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up
Router(config-if) #int se 3/0
Router(config-if)#ip address 172.21.3.3 255.255.255.0 Router(config-if)#no shutdown
Router(config-if)#
%LINK-5-CHANGED: Interface Serial3/0, changed state to up
Router(config-if)#ip address 172.21.3.3 255.255.255.0 %LINEPROTO-5-UPDOWN: Line protocol on Interface Serial3/0, changed state to up
Router(config-if) #int se 2/0
Router(config-if) #clock rate 2000000
Router(config-if) #ip address 172.21.2.3 255.255.255.0
Router(config-if) #no shutdown
Router(config-if)#
%LINK-5-CHANGED: Interface Serial2/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial2/0, changed state to up
Router(config-if)#
```


Ctrl+F6 to exit CLI focus


2. Konfigurasi ip PC







3. Pengujian kesesuain konfigurasi









4. Menampilkan ip route






```
Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 172.21.3.3, timeout is 2 seconds:
11111
Success rate is 100 percent (5/5), round-trip min/avg/max = 1/3/8 ms
Router#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B -
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS
inter area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route
Gateway of last resort is not set
     172.21.0.0/24 is subnetted, 3 subnets
        172.21.1.0 is directly connected, Serial2/0
        172.21.3.0 is directly connected, Serial3/0
C
C
        172.21.20.0 is directly connected, FastEthernet0/0
Router#
```

Ctrl+F6 to exit CLI focus


Тор

Copy

Paste





6. Trace PC leo ke PC aries



7. Trace dari PC leo ke router eagle (172.21.1.1)

8. Melakukan ip route pada masing masing router





```
Router > en
Router # conf
Configuring from terminal, memory, or network [terminal]?
Enter configuration commands, one per line. End with CNTL/Z.
Router (config) # ip route 172.21.10.0 255.255.255.0 172.21.2.1
Router (config) # ip route 172.21.20.0 255.255.255.0 172.21.3.2
Router (config) #

Ctrl+F6 to exit CLI focus

Copy
Paste
```

9. Ping PC leo ke PC aries dan tracer PC leo ke PC aries

```
C:\>ping 172.21.20.2

Pinging 172.21.20.2 with 32 bytes of data:

Request timed out.

Reply from 172.21.20.2: bytes=32 time=130ms TTL=126

Reply from 172.21.20.2: bytes=32 time=15ms TTL=126

Reply from 172.21.20.2: bytes=32 time=lms TTL=126

Ping statistics for 172.21.20.2:

Packets: Sent = 4, Received = 3, Lost = 1 (25% loss),


Approximate round trip times in milli-seconds:

Minimum = lms, Maximum = 130ms, Average = 48ms

C:\>
```

```
C:\>tracert 172.21.20.2
 Tracing route to 172.21.20.2 over a maximum of 30 hops:
       0 ms
                 0 ms
                           0 ms
                                     172.21.10.10
      1 ms
                 1 ms
                           4 ms
                                     172.21.1.2
                 13 ms
       0 ms
                           0 ms
                                     172.21.20.2
 Trace complete.
 C:\>
Тор
```

10. Mengubah alamat jaringan pada Leo menjadi 172.21.100.0/24




11. Konfigurasi ip baru pada router eagle

Router#en	
Router#conf	
Configuring from terminal, memory,	or network [terminal]?
Enter configuration commands, one	per line. End with CNTL/Z.
Router(config) #int fa 0/0	
Router(config-if)#ip address 172.2	1.100.10 255.255.255.0
Router(config-if) #no shutdown	
Router(config-if)#	
Ctrl+F6 to exit CLI focus	Сору
	No.
Тор	
4	

12. Menambahkan konfigurasi ip route baru pada router puma dan tiger

Router#conf		
Configuring from terminal, memory, or network [
Enter configuration commands, one per line. En Router(config)#ip route 172.21.100.0 255.255.25		
Router(config)#	0.0 172.21.1.1	
trl+F6 to exit CLI focus	Copy	Paste
arrive to only our roots	СОРУ	, 4010
Top		
ю		
outer>en		
outer#conf		
onfiguring from terminal, memory, or network [t	terminal]?	
nter configuration commands, one per line. End	d with CNTL/Z.	
outer(config) #ip route 172.21.100.0 255.255.255	5.0 172.21.2.1	
outer(config)#		
. 25. V.C. 10		
rl+F6 to exit CLI focus	Copy	Paste

13. Melakukan ping dan tracer dari Leo ke Aries dan Virgo





Тор

Physical Config Desktop Programming Attributes

```
Command Prompt
```

```
Trace complete.
C:\>ping 172.21.30.3
Pinging 172.21.30.3 with 32 bytes of data:
Reply from 172.21.30.3: bytes=32 time=2ms TTL=126
Reply from 172.21.30.3: bytes=32 time=1ms TTL=126
Reply from 172.21.30.3: bytes=32 time=1ms TTL=126
Reply from 172.21.30.3: bytes=32 time=1ms TTL=126
Ping statistics for 172.21.30.3:
   Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
Approximate round trip times in milli-seconds:
   Minimum = 1ms, Maximum = 2ms, Average = 1ms
C:\>tracert 172.21.30.3
Tracing route to 172.21.30.3 over a maximum of 30 hops:
               56 ms
                         0 ms
     0 ms
                                   172.21.100.10
               1 ms
                        0 ms
                                   172.21.2.3
    1 ms
  2
  3 12 ms
               3 ms
                        2 ms
                                   172.21.30.3
Trace complete.
C:\>
```