Nama : Roni Ardianzah

NIM : L200170073

Kelas : B

MODUL07

1. Buatlah topologi seperti pada gambar



2. Konfigurasi router dengan alamat IP :

eagle









puma


puma
Physical
Config
CLI
Attributes
GLOBAL
Settings
Algorithm Settings
ROUTING
Static
RIP
INTERFACE
FastEthernet0/0
FastEthernet1/0
Serial2/0
Serial3/0
FastEthernet4/0
FastEthernet5/0
FastEthernet0/0
Port Status
On
Bandwidth
100 Mbps
10 Mbps
Auto
Duplex
Half Duplex
Full Duplex
Auto
MAC Address
000D.BD69.ACDA
IP Configuration
IP Address
172.21.20.20
Subnet Mask
255.255.255.0
Tx Ring Limit
10
Equivalent IOS Commands
Router(config)#interface FastEthernet0/0
Router(config-if)#ip address 172.21.20.20 255.255.255.0
Router(config-if)#ip address 172.21.20.20 255.255.255.0
Router(config-if)#
Router(config-if)#exit
Router(config)#interface FastEthernet0/0
Router(config-if)#
Top


puma
Physical
Config
CLI
Attributes
GLOBAL
Settings
Algorithm Settings
ROUTING
Static
RIP
INTERFACE
FastEthernet0/0
FastEthernet1/0
Serial2/0
Serial3/0
FastEthernet4/0
FastEthernet5/0
Serial2/0
Port Status
On
Duplex
Full Duplex
Clock Rate
2000000
IP Configuration
IP Address
172.21.1.2
Subnet Mask
255.255.255.0
Tx Ring Limit
10
Equivalent IOS Commands
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#interface FastEthernet0/0
Router(config-if)#
Router(config-if)#exit
Router(config)#interface Serial2/0
Router(config-if)#
Top


puma
Physical
Config
CLI
Attributes
GLOBAL
Settings
Algorithm Settings
ROUTING
Static
RIP
INTERFACE
FastEthernet0/0
FastEthernet1/0
Serial2/0
Serial3/0
FastEthernet4/0
FastEthernet5/0
Serial3/0
Port Status
On
Duplex
Full Duplex
Clock Rate
1200
IP Configuration
IP Address
172.21.3.2
Subnet Mask
255.255.255.0
Tx Ring Limit
10
Equivalent IOS Commands
Router(config-if)#
Router(config-if)#exit
Router(config)#interface Serial2/0
Router(config-if)#
Router(config-if)#exit
Router(config)#interface Serial3/0
Router(config-if)#
Top


puma
Physical
Config
CLI
Attributes
IOS Command Line Interface
Press RETURN to get started.
Router>en
Router#conf term
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#ip route 172.21.10.0 255.255.255.0 172.21.1.1
Router(config)#ip route 172.21.30.0 255.255.255.0 172.21.3.3
Router(config)#exit
Router#
%SYS-5-CONFIG_I: Configured from console by console
Ctrl+F6 to exit CLI focus
Copy
Paste
Top

tiger


tiger
Physical Config CLI Attributes
GLOBAL
Settings
Algorithm Settings
ROUTING
Static
RIP
INTERFACE
FastEthernet0/0
FastEthernet1/0
Serial2/0
Serial3/0
FastEthernet4/0
FastEthernet5/0
FastEthernet0/0
Port Status
On
Bandwidth
100 Mbps
10 Mbps
Auto
Duplex
Half Duplex
Full Duplex
Auto
MAC Address
0004.9AB2.D23B
IP Configuration
IP Address
172.21.30.30
Subnet Mask
255.255.255.0
Tx Ring Limit
10
Equivalent IOS Commands
Router>enable
Router#
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#interface FastEthernet0/0
Router(config-if)#
Top


tiger
Physical Config CLI Attributes
GLOBAL
Settings
Algorithm Settings
ROUTING
Static
RIP
INTERFACE
FastEthernet0/0
FastEthernet1/0
Serial2/0
Serial3/0
FastEthernet4/0
FastEthernet5/0
Serial2/0
Port Status
On
Duplex
Full Duplex
Clock Rate
2000000
IP Configuration
IP Address
172.21.3.3
Subnet Mask
255.255.255.0
Tx Ring Limit
10
Equivalent IOS Commands
Router(config-if)#
Router(config-if)#exit
Router(config)#interface FastEthernet1/0
Router(config-if)#
Router(config-if)#exit
Router(config)#interface Serial2/0
Router(config-if)#
Top


tiger
Physical Config CLI Attributes
GLOBAL
Settings
Algorithm Settings
ROUTING
Static
RIP
INTERFACE
FastEthernet0/0
FastEthernet1/0
Serial2/0
Serial3/0
FastEthernet4/0
FastEthernet5/0
Serial3/0
Port Status
On
Duplex
Full Duplex
Clock Rate
2000000
IP Configuration
IP Address
172.21.2.3
Subnet Mask
255.255.255.0
Tx Ring Limit
10
Equivalent IOS Commands
Router(config-if)#
Router(config-if)#exit
Router(config)#interface Serial2/0
Router(config-if)#
Router(config-if)#exit
Router(config)#interface Serial3/0
Router(config-if)#
Top


tiger
Physical Config CLI Attributes
IOS Command Line Interface
Press RETURN to get started.
Router>en
Router#conf term
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#ip route 172.21.10.0 255.255.255.0 172.21.2.1
Router(config)#ip route 172.21.20.0 255.255.255.0 172.21.3.2
Router(config)#exit
Router#
%SYS-5-CONFIG_I: Configured from console by console
Ctrl+F6 to exit CLI focus
Copy
Paste
Top

3. konfigurasi tiap PC dengan nama dan alamat IP :







4. PING dari PC Leo ke router eagle

```
C:\>ping 172.21.1.1

Pinging 172.21.1.1 with 32 bytes of data:

Reply from 172.21.1.1: bytes=32 time=1ms TTL=255
Reply from 172.21.1.1: bytes=32 time<1ms TTL=255
Reply from 172.21.1.1: bytes=32 time<1ms TTL=255
Reply from 172.21.1.1: bytes=32 time<1ms TTL=255

Ping statistics for 172.21.1.1:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
Approximate round trip times in milli-seconds:
    Minimum = 0ms, Maximum = 1ms, Average = 0ms

C:\>
```

PING dari PC aries ke router puma

```
C:\>ping 172.21.1.2

Pinging 172.21.1.2 with 32 bytes of data:

Reply from 172.21.1.2: bytes=32 time<1ms TTL=255
Reply from 172.21.1.2: bytes=32 time<1ms TTL=255
Reply from 172.21.1.2: bytes=32 time<1ms TTL=255
Reply from 172.21.1.2: bytes=32 time<1ms TTL=255

Ping statistics for 172.21.1.2:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
Approximate round trip times in milli-seconds:
    Minimum = 0ms, Maximum = 0ms, Average = 0ms

C:\>
```

PING dari PC virgo ke router tiger