

RUN POD GPU : STEPS

1. Push your files to GITHUB

Make sure your code is finalized and the requirements file is ready. Push the code to github.

(Better to run small epochs for small batch size in local device)

2. Generate ssh key

a. Open terminal

For windows:

Generate ssh key:

➔ **ssh-keygen -t ed25519 -C "runpod"**

See your ssh keys

➔ **ls ~/.ssh**

Generate public key

➔ **cat ~/.ssh/id_ed25519.pub**

```
PS C:\Users\Lenovo Loq> ssh-keygen -t ed25519 -C "runpod"
Generating public/private ed25519 key pair.
Enter file in which to save the key (C:\Users\Lenovo Loq\.ssh/id_ed25519):
C:\Users\Lenovo Loq\.ssh/id_ed25519 already exists.
Overwrite (y/n)?
PS C:\Users\Lenovo Loq> ls ~/.ssh

Directory: C:\Users\Lenovo Loq\.ssh

Mode                LastWriteTime         Length Name
----                -
-a-----         2/12/2026 12:41 PM             308 config
-a-----         2/9/2026 12:51 PM             399 id_ed25519
-a-----         2/11/2026  8:35 PM             298 id_ed25519.ppk
-a-----         2/9/2026 12:51 PM              89 id_ed25519.pub
-a-----         2/12/2026 12:42 PM            3435 known_hosts
-a-----         2/12/2026 12:42 PM            2673 known_hosts.old

PS C:\Users\Lenovo Loq> cat ~/.ssh/id_ed25519.pub
ssh-ed25519 iaGWHJwr0bcSafpulfzTDvL1zcpvvdMR01 runpod
PS C:\Users\Lenovo Loq> |
```

3. Update public key on runpod


a. Go to :

Runpod -> Account -> settings

or


<https://console.runpod.io/user/settings>

b. Scroll down to SSH public keys, paste your generated public key and update public key.

The screenshot shows the 'SSH public keys' section of the Runpod user settings. At the top, it says 'SSH public keys' with a small upward arrow icon. Below this is a descriptive paragraph: 'Adding public keys to your account lets you access pods via terminal using the matching private key. You can add multiple keys, separated by a newline (up to 65500 characters). Runpod automatically adds these keys to your Pod's authorized_keys file, making it easy to connect via SSH using the pod's public IP.' Underneath the text is a large, empty text input field with a placeholder label 'SSH public key'. Below the input field, the character count '0/65500 characters' is displayed. At the bottom left of the section is a blue button labeled 'Update public key'.

c. You can add multiple keys, separated by a new line

4. Deploy a POD/GPU (on demand)



Make sure to allocate enough space for your task.

Pod Template Overrides

Container image
This can be a public image from Docker Hub or a private image from your own registry.

+ Select Registry Auth + Start Command

Container Disk
Temporary storage that will be erased when the Pod is stopped.

Volume Disk
Persistent storage mounted to /workspace that will be erased when the Pod is terminated.

Volume Mount Path

Expose HTTP Ports (Max 10)

Expose TCP Ports

Environment variables

Clear Overrides Set Overrides

After deploying the pod you will see an instance created

Name	Utilization	Memory	Disk	Compute type	Cost	
 plastic_crimson_carp h7ns3ecp9kqx0d				 RTX 2000 Ada x1	\$0.25/hr	
10 per page						
< Page 1 of 1 >						

4. Connect your device to runpod

a. Copy the ssh key of the pod



b. Open VS code

c. Ctrl + Shift + P

i. Remote-SSH: Connect to Host

ii. Add New SSH Host

iii. Paste your run pod SSH

iv. Select the path where you had your .ssh folder

d. Ctrl + Shift + P

i. Connect to Host

ii. Check IP of your runpod

SSH over exposed TCP

Connect to your Pod using SSH over a direct TCP connection. (Supports SCP & SFTP)

```
$ ssh root@213.173.99.23 -p 16089 -i ~/.ssh/id_ed25519
```



Here, the IP is 213.173.99.23, which is your SSH host.

This opens a new window. Select Linux and Continue.

5. Clone your GitHub repo

6. Enter your folder directory :

Simply click the “OPEN FOLDER” icon

7. Create virtual environment

```
python3 -m venv venv_name
```

```
source venv_name/bin/activate
```

8. Open terminal and check your GPU configuration

```
nvidia-smi
```

9. Transfer your dataset to the GPU storage

a. Through hugging face

b. Through WinSCP

i. Download WinSCP

Login

New Site

Session

File protocol:
SFTP

Host name: Port number: 22

User name: Password:

Save Advanced...

Tools Manage Login Close Help

☒ Show Login dialog on startup and when the last session is closed


```
SSH over exposed TCP
Connect to your Pod using SSH over a direct TCP connection. (Supports SCP & SFTP)
$ ssh root@213.173.99.23 -p 16089 -i ~/.ssh/id_ed25519
```

Host name port

ii. User name = root


iii. Leave the password field blank

iv. Tools -> Run PuTTYgen




v. Load an existing private key file

- go to your .ssh folder where the generated ssh is located



- **Select all files**
- **Choose the ssh file**

vi. Go to advanced -> authentication and choose the private key file in .ppk format



vii. The connection is established, now you can access the GPU storage from your device