

TYPOGRAPHY · ONE READING SIZE PER VENUE

Every list, card and table
now reads at one size.

LIST TAKEAWAY • WAS 21PT

A takeaway row reads at the body size now.

Rows used to sit a full step above card text.

The venue scaled them, but never brought them in line.

Now a row, a card and a cell match on every slide.

A list at laptop holds twice the rows it did.

KEY INSIGHT

A reader's eye no longer has to re-focus between slides.

Card bodies set the size everything else now meets.

Lists come down.

From 21pt to 16pt, so a list holds more rows.

Tables come up.

From 13.5pt to 16pt, so a cell reads from farther away.

Cards stay put.

They were already at the reading size.

KEY INSIGHT

The body role, `--fs-body`, is the one reading size.

LIST-TABULAR • WAS 13.5PT

A tabular row reads at the same size as a card.

- | | | |
|----|------------|---|
| 01 | Laptop | 16pt, for a PDF read on your own screen. |
| 02 | Huddle | 18.5pt, for four to six people around a TV. |
| 03 | Conference | 20.9pt, for a room of ten to thirty. |
| 04 | Hall | 24.1pt, for a stage screen. |

KEY INSIGHT

The venue multiplies one size instead of three.

TABLE • WAS 13.5PT

A table cell now reads at the body size too.

VENUE	READING TEXT	CODE	TABLE ROWS AT 12 WORDS
Laptop	16pt	13.5pt	10
Huddle	18.5pt	15.5pt	8
Conference	20.9pt	17.5pt	7
Hall	24.1pt	20.2pt	3

KEY INSIGHT

Bigger cells cost rows: split a long table instead of shrinking it.

Glossary

R – E

TERM	DEFINITION
Reading text	Text read line by line, several items to a slide.
Display text	One sentence or number that is the slide, set bigger on purpose.
Venue	The room a deck is shown in, which sets one multiplier for all type.
Exception	A component that keeps its own size, named in the decision note.

CODE • STAYS AT 13.5PT

Code keeps one step down, because it cannot wrap.

```
// A code line that wraps changes what it says, so code keeps  
// its column budget: about 102 columns at laptop.  
const reading = venueScale * FS_BODY;           // 16pt at laptop  
const code = venueScale * FS_BODY_COMPACT;       // 13.5pt at laptop
```

KEY INSIGHT

Code is the one reading exception, by the owner's ruling.

One reading size, in every room.

typography.md §7 · one reading size