```
_id=uno
archive_file_path=C:\Users\jordan\AppData\Local\arduino\sketches\
EFEA967F2B39B2CBA42B900B13682C65/{archive_file}
bootloader.extended_fuses=0xFD
bootloader.file=optiboot/optiboot_atmega328.hex
bootloader.high_fuses=0xDE
bootloader.lock_bits=0x0F
bootloader.low_fuses=0xFF
bootloader.tool=avrdude
bootloader.tool.default=avrdude
bootloader.unlock_bits=0x3F
build.arch=AVR
build.board=AVR_UNO
build.board.platform.path=C:\Users\jordan\AppData\Local\Arduino15\packages\
arduino\hardware\avr\1.8.8
build.core=arduino
build.core.path=C:\Users\jordan\AppData\Local\Arduino15\packages\arduino\
hardware\avr\1.8.8\cores\arduino
build.core.platform.path=C:\Users\jordan\AppData\Local\Arduino15\packages\
arduino\hardware\avr\1.8.8
build.extra_flags=
build.f_cpu=16000000L
build.fqbn=arduino:avr:uno
build.library_discovery_phase=0
build.mcu=atmega328p
build.path=C:\Users\jordan\AppData\Local\arduino\sketches\
EFEA967F2B39B2CBA42B900B13682C65
build.project_name=LED_binary_counter.ino
build.source.path=C:\Users\jordan\Desktop\Arduino_projects\LED_binary_counter
build.system.path=C:\Users\jordan\AppData\Local\Arduino15\packages\arduino\
hardware\avr\1.8.8\system
build.usb_flags=-DUSB_VID={build.vid} -DUSB_PID={build.pid} '-
DUSB_MANUFACTURER="Unknown"' '-DUSB_PRODUCT={build.usb_product}'
build.usb_manufacturer="Unknown"
build.variant=standard
build.variant.path=C:\Users\jordan\AppData\Local\Arduino15\packages\arduino\
hardware\avr\1.8.8\variants\standard
compiler.S.extra_flags=
compiler.S.flags=-c -g -x assembler-with-cpp -flto -MMD
compiler.ar.cmd=avr-gcc-ar
compiler.ar.extra_flags=
compiler.ar.flags=rcs
compiler.c.cmd=avr-gcc
compiler.c.elf.cmd=avr-gcc
compiler.c.elf.extra_flags=
compiler.c.elf.flags=-w -Os -g -flto -fuse-linker-plugin -Wl,--gc-sections
compiler.c.extra_flags=
compiler.c.flags=-c -g -Os -w -std=gnu11 -ffunction-sections -fdata-sections -
MMD -flto -fno-fat-lto-objects
compiler.cpp.cmd=avr-g++
compiler.cpp.extra_flags=
compiler.cpp.flags=-c -g -Os -w -std=gnu++11 -fpermissive -fno-exceptions -
ffunction-sections -fdata-sections -fno-threadsafe-statics -Wno-error=narrowing
-MMD -flto
compiler.elf2hex.cmd=avr-objcopy
compiler.elf2hex.extra_flags=
compiler.elf2hex.flags=-O ihex -R .eeprom
compiler.ldflags=
compiler.libraries.ldflags=
compiler.objcopy.cmd=avr-objcopy
compiler.objcopy.eep.extra_flags=
compiler.objcopy.eep.flags=-O ihex -j .eeprom --set-section-
flags=.eeprom=alloc,load --no-change-warnings --change-section-lma .eeprom=0
```

```
compiler.path=C:\Users\jordan\AppData\Local\Arduino15\packages\arduino\tools\
avr-gcc\7.3.0-atmel3.6.1-arduino7/bin/
compiler.size.cmd=avr-size
compiler.warning_flags=-w
compiler.warning_flags.all=-Wall -Wextra
compiler.warning_flags.default=
compiler.warning_flags.more=-Wall
compiler.warning_flags.none=-w
extra.time.dst=0
extra.time.local=1790859825
extra.time.utc=1790823825
extra.time.zone=36000
ide_version=10607
name=Arduino UNO
pid.0=0x0043
pid.1=0x0001
pid.2=0x0043
pid.3=0x0243
pid.4=0x006A
pluggable_discovery.required.0=builtin:serial-discovery
pluggable_discovery.required.1=builtin:mdns-discovery
pluggable_monitor.required.serial=builtin:serial-monitor
preproc.includes.flags=-w -x c++ -M -MG -MP
preproc.macros.flags=-w -x c++ -E -CC
recipe.S.o.pattern="C:\Users\jordan\AppData\Local\Arduino15\packages\arduino\
tools\avr-gcc\7.3.0-atmel3.6.1-arduino7/bin/avr-gcc" -c -g -x assembler-with-cpp
-flto -MMD -mmcu=atmega328p -DF_CPU=16000000L -DARDUINO=10607 -DARDUINO_AVR_UNO
-DARDUINO_ARCH_AVR   {includes} "{source_file}" -o "{object_file}"
recipe.ar.pattern="C:\Users\jordan\AppData\Local\Arduino15\packages\arduino\
tools\avr-gcc\7.3.0-atmel3.6.1-arduino7/bin/avr-gcc-ar" rcs  "C:\Users\jordan\
AppData\Local\arduino\sketches\EFEA967F2B39B2CBA42B900B13682C65/{archive_file}"
"{object_file}"
recipe.c.combine.pattern="C:\Users\jordan\AppData\Local\Arduino15\packages\
arduino\tools\avr-gcc\7.3.0-atmel3.6.1-arduino7/bin/avr-gcc" -w -Os -g -flto -
fuse-linker-plugin -Wl,--gc-sections -mmcu=atmega328p   -o "C:\Users\jordan\
AppData\Local\arduino\sketches\EFEA967F2B39B2CBA42B900B13682C65/
LED_binary_counter.ino.elf" {object_files}  "C:\Users\jordan\AppData\Local\
arduino\sketches\EFEA967F2B39B2CBA42B900B13682C65/{archive_file}" "-LC:\Users\
jordan\AppData\Local\arduino\sketches\EFEA967F2B39B2CBA42B900B13682C65" -lm
recipe.c.o.pattern="C:\Users\jordan\AppData\Local\Arduino15\packages\arduino\
tools\avr-gcc\7.3.0-atmel3.6.1-arduino7/bin/avr-gcc" -c -g -Os -w -std=gnu11 -
ffunction-sections -fdata-sections -MMD -flto -fno-fat-lto-objects -
mmcu=atmega328p -DF_CPU=16000000L -DARDUINO=10607 -DARDUINO_AVR_UNO -
DARDUINO_ARCH_AVR   {includes} "{source_file}" -o "{object_file}"
recipe.cpp.o.pattern="C:\Users\jordan\AppData\Local\Arduino15\packages\arduino\
tools\avr-gcc\7.3.0-atmel3.6.1-arduino7/bin/avr-g++" -c -g -Os -w -std=gnu++11 -
fpermissive -fno-exceptions -ffunction-sections -fdata-sections -fno-threadsafe-
statics -Wno-error=narrowing -MMD -flto -mmcu=atmega328p -DF_CPU=16000000L -
DARDUINO=10607 -DARDUINO_AVR_UNO -DARDUINO_ARCH_AVR   {includes} "{source_file}"
-o "{object_file}"
recipe.objcopy.eep.pattern="C:\Users\jordan\AppData\Local\Arduino15\packages\
arduino\tools\avr-gcc\7.3.0-atmel3.6.1-arduino7/bin/avr-objcopy" -O ihex -
j .eeprom --set-section-flags=.eeprom=alloc,load --no-change-warnings --change-
section-lma .eeprom=0  "C:\Users\jordan\AppData\Local\arduino\sketches\
EFEA967F2B39B2CBA42B900B13682C65/LED_binary_counter.ino.elf" "C:\Users\jordan\
AppData\Local\arduino\sketches\EFEA967F2B39B2CBA42B900B13682C65/
LED_binary_counter.ino.eep"
recipe.objcopy.hex.pattern="C:\Users\jordan\AppData\Local\Arduino15\packages\
arduino\tools\avr-gcc\7.3.0-atmel3.6.1-arduino7/bin/avr-objcopy" -O ihex -
R .eeprom  "C:\Users\jordan\AppData\Local\arduino\sketches\
EFEA967F2B39B2CBA42B900B13682C65/LED_binary_counter.ino.elf" "C:\Users\jordan\
AppData\Local\arduino\sketches\EFEA967F2B39B2CBA42B900B13682C65/
LED_binary_counter.ino.hex"
recipe.output.save_file=LED_binary_counter.ino.standard.hex
```

```
recipe.output.tmp_file=LED_binary_counter.ino.hex
recipe.preproc.includes="C:\Users\jordan\AppData\Local\Arduino15\packages\
arduino\tools\avr-gcc\7.3.0-atmel3.6.1-arduino7/bin/avr-g++" -c -g -Os -w -
std=gnu++11 -fpermissive -fno-exceptions -ffunction-sections -fdata-sections -
fno-threadsafe-statics -Wno-error=narrowing -MMD -flto -w -x c++ -M -MG -MP -
mmcu=atmega328p -DF_CPU=16000000L -DARDUINO=10607 -DARDUINO_AVR_UNO -
DARDUINO_ARCH_AVR   {includes} "{source_file}"
recipe.preproc.macros="C:\Users\jordan\AppData\Local\Arduino15\packages\arduino\
tools\avr-gcc\7.3.0-atmel3.6.1-arduino7/bin/avr-g++" -c -g -Os -w -std=gnu++11 -
fpermissive -fno-exceptions -ffunction-sections -fdata-sections -fno-threadsafe-
statics -Wno-error=narrowing -MMD -flto -w -x c++ -E -CC -mmcu=atmega328p -
DF_CPU=16000000L -DARDUINO=10607 -DARDUINO_AVR_UNO -DARDUINO_ARCH_AVR
{includes} "{source_file}" -o "{preprocessed_file_path}"
recipe.size.pattern="C:\Users\jordan\AppData\Local\Arduino15\packages\arduino\
tools\avr-gcc\7.3.0-atmel3.6.1-arduino7/bin/avr-size" -A "C:\Users\jordan\
AppData\Local\arduino\sketches\EFEA967F2B39B2CBA42B900B13682C65/
LED_binary_counter.ino.elf"
recipe.size.regex=^(?:\.text|\.data|\.bootloader)\s+([0-9]+).*
recipe.size.regex.data=^(?:\.data|\.bss|\.noinit)\s+([0-9]+).*
recipe.size.regex.eeprom=^(?:\.eeprom)\s+([0-9]+).*
runtime.hardware.path=C:\Users\jordan\AppData\Local\Arduino15\packages\arduino\
hardware\avr
runtime.ide.path=C:\ProgramData\chocolatey\lib\arduino-cli\tools
runtime.ide.version=10607
runtime.os=windows
runtime.platform.path=C:\Users\jordan\AppData\Local\Arduino15\packages\arduino\
hardware\avr\1.8.8
runtime.tools.arduinoOTA-1.3.0.path=C:\Users\jordan\AppData\Local\Arduino15\
packages\arduino\tools\arduinoOTA\1.3.0
runtime.tools.arduinoOTA.path=C:\Users\jordan\AppData\Local\Arduino15\packages\
arduino\tools\arduinoOTA\1.3.0
runtime.tools.avr-gcc-7.3.0-atmel3.6.1-arduino7.path=C:\Users\jordan\AppData\
Local\Arduino15\packages\arduino\tools\avr-gcc\7.3.0-atmel3.6.1-arduino7
runtime.tools.avr-gcc.path=C:\Users\jordan\AppData\Local\Arduino15\packages\
arduino\tools\avr-gcc\7.3.0-atmel3.6.1-arduino7
runtime.tools.avrdude-8.0.0-arduino1.path=C:\Users\jordan\AppData\Local\
Arduino15\packages\arduino\tools\avrdude\8.0.0-arduino1
runtime.tools.avrdude.path=C:\Users\jordan\AppData\Local\Arduino15\packages\
arduino\tools\avrdude\8.0.0-arduino1
runtime.tools.ctags-5.8-arduino11.path=C:\Users\jordan\AppData\Local\Arduino15\
packages\builtin\tools\ctags\5.8-arduino11
runtime.tools.ctags.path=C:\Users\jordan\AppData\Local\Arduino15\packages\
builtin\tools\ctags\5.8-arduino11
runtime.tools.dfu-discovery-0.1.2.path=C:\Users\jordan\AppData\Local\Arduino15\
packages\builtin\tools\dfu-discovery\0.1.2
runtime.tools.dfu-discovery.path=C:\Users\jordan\AppData\Local\Arduino15\
packages\builtin\tools\dfu-discovery\0.1.2
runtime.tools.mdns-discovery-1.1.0.path=C:\Users\jordan\AppData\Local\Arduino15\
packages\builtin\tools\mdns-discovery\1.1.0
runtime.tools.mdns-discovery.path=C:\Users\jordan\AppData\Local\Arduino15\
packages\builtin\tools\mdns-discovery\1.1.0
runtime.tools.serial-discovery-1.5.2.path=C:\Users\jordan\AppData\Local\
Arduino15\packages\builtin\tools\serial-discovery\1.5.2
runtime.tools.serial-discovery.path=C:\Users\jordan\AppData\Local\Arduino15\
packages\builtin\tools\serial-discovery\1.5.2
runtime.tools.serial-monitor-0.15.0.path=C:\Users\jordan\AppData\Local\
Arduino15\packages\builtin\tools\serial-monitor\0.15.0
runtime.tools.serial-monitor.path=C:\Users\jordan\AppData\Local\Arduino15\
packages\builtin\tools\serial-monitor\0.15.0
sketch_path=C:\Users\jordan\Desktop\Arduino_projects\LED_binary_counter
software=ARDUINO
tools.arduino_ota.cmd=C:\Users\jordan\AppData\Local\Arduino15\packages\arduino\
tools\arduinoOTA\1.3.0/bin/arduinoOTA
```

```
tools.arduino_ota.upload.pattern="{cmd}" -address {upload.port.address} -port
{upload.port.properties.port} -sketch "C:\Users\jordan\AppData\Local\arduino\
sketches\EFEA967F2B39B2CBA42B900B13682C65/LED_binary_counter.ino.hex" -upload
{upload.port.properties.endpoint_upload} -sync
{upload.port.properties.endpoint_sync} -reset
{upload.port.properties.endpoint_reset} -sync_exp
{upload.port.properties.sync_return}
tools.avrdude.bootloader.params.quiet=-q -q
tools.avrdude.bootloader.params.verbose=-v
tools.avrdude.bootloader.pattern="{cmd.path}" "-C{config.path}"
{bootloader.verbose} -patmega328p -c{protocol} {program.extra_params} "-
Uflash:w:C:\Users\jordan\AppData\Local\Arduino15\packages\arduino\hardware\avr\
1.8.8/bootloaders/optiboot/optiboot_atmega328.hex:i" -Ulock:w:0x0F:m
tools.avrdude.cmd.path={path}/bin/avrdude
tools.avrdude.config.path={path}/etc/avrdude.conf
tools.avrdude.erase.params.quiet=-q -q
tools.avrdude.erase.params.verbose=-v
tools.avrdude.erase.pattern="{cmd.path}" "-C{config.path}" {erase.verbose} -
patmega328p -c{protocol} {program.extra_params} -e -Ulock:w:0x3F:m -
Uefuse:w:0xFD:m -Uhfuse:w:0xDE:m -Ulfuse:w:0xFF:m
tools.avrdude.network_cmd=C:\Users\jordan\AppData\Local\Arduino15\packages\
arduino\tools\arduinoOTA\1.3.0/bin/arduinoOTA
tools.avrdude.path=C:\Users\jordan\AppData\Local\Arduino15\packages\arduino\
tools\avrdude\8.0.0-arduino1
tools.avrdude.program.params.noverify=-V
tools.avrdude.program.params.quiet=-q -q
tools.avrdude.program.params.verbose=-v
tools.avrdude.program.pattern="{cmd.path}" "-C{config.path}" {program.verbose}
{program.verify} -patmega328p -c{protocol} {program.extra_params} "-Uflash:w:C:\
Users\jordan\AppData\Local\arduino\sketches\EFEA967F2B39B2CBA42B900B13682C65/
LED_binary_counter.ino.hex:i"
tools.avrdude.program.verify=
tools.avrdude.upload.network_pattern="{network_cmd}" -address {serial.port} -
port {upload.network.port} -sketch "C:\Users\jordan\AppData\Local\arduino\
sketches\EFEA967F2B39B2CBA42B900B13682C65/LED_binary_counter.ino.hex" -upload
{upload.network.endpoint_upload} -sync {upload.network.endpoint_sync} -reset
{upload.network.endpoint_reset} -sync_exp {upload.network.sync_return}
tools.avrdude.upload.params.noverify=-V
tools.avrdude.upload.params.quiet=-q -q
tools.avrdude.upload.params.verbose=-v
tools.avrdude.upload.pattern="{cmd.path}" "-C{config.path}" {upload.verbose}
{upload.verify} -patmega328p -carduino "-P{serial.port}" -b115200 -D "-
Uflash:w:C:\Users\jordan\AppData\Local\arduino\sketches\
EFEA967F2B39B2CBA42B900B13682C65/LED_binary_counter.ino.hex:i"
tools.avrdude.upload.verify=
tools.avrdude_remote.upload.pattern=/usr/bin/run-avrdude /tmp/sketch.hex
{upload.verbose} -patmega328p
upload.maximum_data_size=2048
upload.maximum_size=32256
upload.protocol=arduino
upload.speed=115200
upload.tool=avrdude
upload.tool.default=avrdude
upload.tool.network=arduino_ota
upload_port.0.pid=0x0043
upload_port.0.vid=0x2341
upload_port.1.pid=0x0001
upload_port.1.vid=0x2341
upload_port.2.pid=0x0043
upload_port.2.vid=0x2A03
upload_port.3.pid=0x0243
upload_port.3.vid=0x2341
upload_port.4.pid=0x006A
upload_port.4.vid=0x2341
```

```
upload_port.5.board=uno
version=1.8.8
vid.0=0x2341
vid.1=0x2341
vid.2=0x2A03
vid.3=0x2341
vid.4=0x2341



    Directory: C:\Users\jordan\AppData\Local\Arduino15\packages\arduino\
hardware\avr\1.8.8\cores\arduino


Mode                 LastWriteTime         Length Name
----                 -------------         ------ ----
-a----        23/09/2026   2:30 PM           7613 Arduino.h


    Directory: C:\Users\jordan\AppData\Local\Arduino15\packages\arduino\
hardware\avr\1.8.8\firmwares\wifishield\wifi
    HD\src\SOFTWARE_FRAMEWORK\BOARDS\ARDUINO


Mode                 LastWriteTime         Length Name
----                 -------------         ------ ----
-a----        23/09/2026   2:30 PM           8812 arduino.h


    Directory: C:\Users\jordan\AppData\Local\Arduino15\packages\arduino\
hardware\avr\1.8.8\firmwares\wifishield\wifi
    _dnld\src\SOFTWARE_FRAMEWORK\BOARDS\ARDUINO


Mode                 LastWriteTime         Length Name
----                 -------------         ------ ----
-a----        23/09/2026   2:30 PM           8684 arduino.h
```