DEVOPS – 10.03.2026






EC2 > Instances
EC2
Dashboard
AWS Global View
Events
Instances
Instances
Instance Types
Launch Templates
Spot Requests
Savings Plans
Reserved Instances
Dedicated Hosts
Capacity Reservations
Capacity Manager New
Images
AMIs
Instances (1) Info
Connect
Instance state
Actions
Launch instances
All states
Name
Instance ID
Instance state
Instance type
Status check
Alarm status
dockerhost
i-048ada3c159b1a20b
Running
t3.micro
Initializing
View alarms +
us-east-1f
Select an instance


Instances (1/1) Info
Last updated less than a minute ago
Connect
Instance state
Actions
Find Instance by attribute or tag (case-sensitive)
All states
Name
Instance ID
Instance state
Instance type
Status check
dockerhost
i-048ada3c159b1a20b
Running
t3.micro
3/3 checks passed
i-048ada3c159b1a20b (dockerhost)
Details
Status and alarms
Monitoring
Security
Networking
Storage
Tags
Instance summary Info


Instances (1/1) Info
Last updated less than a minute ago
Connect
Instance state
Actions
Launch instances
Find Instance by attribute or tag (case-sensitive)
All states
Name
Instance ID
Instance state
Instance type
Status check
Alarm status
Availability Zo
dockerhost
i-048ada3c159b1a20b
Running
t3.micro
3/3 checks passed
View alarms +
us-east-1f
i-048ada3c159b1a20b (dockerhost)
IAM role
–
Owner ID
988176744101
Launch time
Tue Mar 10 2026 09:51:43 GMT+0530 (India Standard Time)
Security groups
sg-02d1ff81fc1f7a7f0 (launch-wizard-1)



Click security group link





```
• Direct SSH      : ✔
• SSH compression : ✔
• SSH-browser     : ✔
• X11-forwarding  : ✘  (disabled or not supported by server)

► For more info, ctrl+click on help or visit our website.

       #
  ~\_  ####_        Amazon Linux 2023
 ~~ \_#####\
 ~~    \###|
 ~~      \#/ ___   https://aws.amazon.com/linux/amazon-linux-2023
  ~~      V~' '->
   ~~~         /
     ~~._.   _/
        _/ _/
      _m/'
Last login: Tue Mar 10 04:39:46 2026 from 106.192.69.190
[ec2-user@ip-172-31-75-220 ~]$ ls
[ec2-user@ip-172-31-75-220 ~]$ sudo -i
[root@ip-172-31-75-220 ~]# ls
dockerfile  index.html
[root@ip-172-31-75-220 ~]# vi dockerfile
[root@ip-172-31-75-220 ~]# docker build -t cusimage1 .
[+] Building 0.3s (7/7) FINISHED                                                    docker:default
 => [internal] load build definition from dockerfile                                          0.0s
 => => transferring dockerfile: 141B                                                          0.0s
 => [internal] load metadata for docker.io/library/httpd:latest                               0.2s
 => [internal] load .dockerignore                                                             0.0s
 => => transferring context: 2B                                                               0.0s
 => [internal] load build context                                                             0.0s
 => => transferring context: 91B                                                              0.0s
 => CACHED [1/2] FROM docker.io/library/httpd:latest@sha256:96b1e8f69ee3adde956e819f7a7c3e766edef7ad88a26a491734015e5c595333  0.0s
 => [2/2] COPY index.html /htdocs/                                                            0.0s
 => exporting to image                                                                        0.0s
 => => exporting layers                                                                       0.0s
 => => writing image sha256:8d4cb688de653c0ff736bfcef6aabd858e768ebd862aa4125c6519fc4e93969d  0.0s
 => => naming to docker.io/library/cusimage1                                                  0.0s
[root@ip-172-31-75-220 ~]# docker ps
CONTAINER ID   IMAGE          COMMAND                  CREATED          STATUS          PORTS                                   NAMES
a0663764b4a3   customimage    "httpd-foreground"       16 minutes ago   Up 16 minutes   0.0.0.0:81->80/tcp, :::81->80/tcp       testcon
[root@ip-172-31-75-220 ~]#
```

```
[root@ip-172-31-75-220 ~]# docker ps
CONTAINER ID   IMAGE          COMMAND                  CREATED          STATUS          PORTS                                   NAMES
a0663764b4a3   customimage    "httpd-foreground"       16 minutes ago   Up 16 minutes   0.0.0.0:81->80/tcp, :::81->80/tcp       testcon
[root@ip-172-31-75-220 ~]# docker rm -f testcon
testcon
[root@ip-172-31-75-220 ~]#
```

```
[root@ip-172-31-75-220 ~]# docker run -d --name testcon -p 81:80 cusimage1
3239da43c575b2d8e40c7f9b00fe79b5521856135069a1280516157e369731ca
[root@ip-172-31-75-220 ~]#
```

```
root@3239da43c575:/usr/local/apache2/htdocs# cat index.html
<!DOCTYPE HTML PUBLIC "-//W3C//DTD HTML 4.01//EN" "http://www.w3.org/TR/html4/strict.dtd">
<html>
<head>
<title>It works! Apache httpd</title>
</head>
<body>
<p>It works!</p>
</body>
</html>
root@3239da43c575:/usr/local/apache2/htdocs# cd /htdocs
root@3239da43c575:/htdocs# ls
index.html
root@3239da43c575:/htdocs# ^C
root@3239da43c575:/htdocs# exit
exit
[root@ip-172-31-75-220 ~]# vi dockerfile
[root@ip-172-31-75-220 ~]# docker build -t cusimage2 .
[+] Building 0.3s (7/7) FINISHED                                                    docker:default
 => [internal] load build definition from dockerfile                                          0.0s
 => => transferring dockerfile: 159B                                                          0.0s
 => [internal] load metadata for docker.io/library/httpd:latest                               0.2s
 => [internal] load .dockerignore                                                             0.0s
 => => transferring context: 2B                                                               0.0s
 => [internal] load build context                                                             0.0s
 => => transferring context: 91B                                                              0.0s
 => CACHED [1/2] FROM docker.io/library/httpd:latest@sha256:96b1e8f69ee3adde956e819f7a7c3e766edef7ad88a26a491734015e5c595333  0.0s
 => [2/2] COPY index.html /usr/local/apache2/htdocs/                                          0.0s
 => exporting to image                                                                        0.0s
 => => exporting layers                                                                       0.0s
 => => writing image sha256:99b33774ea8ab79b59a858772018584581d48f7bfe7298dc4486b14b756144  0.0s
 => => naming to docker.io/library/cusimage2                                                  0.0s
[root@ip-172-31-75-220 ~]# docker run -d --name testcon1 -p 82:80 cusimage2
e631a4282f158cbe9bb49cf5f93aa7f0ad5dec8a5a29ec1d49ba02ea48ef158c
[root@ip-172-31-75-220 ~]# docker ps
CONTAINER ID   IMAGE          COMMAND                  CREATED          STATUS          PORTS                                   NAMES
e631a4282f15   cusimage2      "httpd-foreground"       5 seconds ago    Up 5 seconds    0.0.0.0:82->80/tcp, :::82->80/tcp       testcon1
3239da43c575   cusimage1      "httpd-foreground"       5 minutes ago    Up 5 minutes    0.0.0.0:81->80/tcp, :::81->80/tcp       testcon
[root@ip-172-31-75-220 ~]# cat dockerfile
FROM httpd:latest
COPY index.html /usr/local/apache2/htdocs/
```

Amazon ECR > Private registry > Repositories > Create private repository

Create private repository

General settings

Repository name
Enter a concise name. Repositories support namespaces, which you can use to group similar repositories.

988176744101.dkr.ecr.us-east-1.amazonaws.com/ *namespace/repo-name*

0 out of 256 characters maximum (2 minimum). The name must start with a letter and can only contain lowercase letters, numbers, and special characters _-/.

Image tag settings Info

Image tag mutability
Choose the tag mutability setting.

- Mutable
  Image tags can be overwritten.
- Immutable
  Image tags can't be overwritten.

Mutable tag exclusions
Tags that match these filters will be immutable (can't be overwritten). Using wildcards (*) will match zero or more image tag characters.

Amazon ECR > Private registry > Repositories > Create private repository

7 out of 256 characters maximum (2 minimum). The name must start with a letter and can only contain lowercase letters, numbers, and special characters _-/.

Image tag settings Info

Image tag mutability
Choose the tag mutability setting.

- Mutable
  Image tags can be overwritten.
- Immutable
  Image tags can't be overwritten.

Mutable tag exclusions
Tags that match these filters will be immutable (can't be overwritten). Using wildcards (*) will match zero or more image tag characters.

Add filter

Filters must only contain letters, numbers, and special characters (_*-). Each filter is limited to 128 characters, 2 wildcards (*), and you can add up to 5 filters in the exclusion list

Encryption settings Info

⚠ The encryption settings for a repository can't be changed once the repository is created.

Push commands for testecr

macOS / Linux | Windows

Make sure that you have the latest version of the AWS CLI and Docker installed. For more information, see Getting Started with Amazon ECR.

Use the following steps to authenticate and push an image to your repository. For additional registry authentication methods, including the Amazon ECR credential helper, see Registry Authentication.

1. Retrieve an authentication token and authenticate your Docker client to your registry. Use the AWS CLI:

```
aws ecr get-login-password --region us-east-1 | docker login --username AWS --password-stdin 988176744101.dkr.ecr.us-east-1.amazonaws.com
```

   Note: If you receive an error using the AWS CLI, make sure that you have the latest version of the AWS CLI and Docker installed.

2. Build your Docker image using the following command. For information on building a Docker file from scratch see the instructions here. You can skip this step if your image is already built:

```
docker build -t testecr .
```

3. After the build completes, tag your image so you can push the image to this repository:

```
docker tag testecr:latest 988176744101.dkr.ecr.us-east-1.amazonaws.com/testecr:latest
```

4. Run the following command to push this image to your newly created AWS repository:

Close

My security credentials Root user Info

The root user has access to all AWS resources in this account, and we recommend following best practices. To learn more about the types of AWS credentials and how they're used, see AWS Security Credentials in AWS General Reference

Account details

Actions

Account name -	Email address -
AWS account ID 988176744101	Canonical user ID -

IAM > Security credentials

Identity and Access Management (IAM)

Search IAM

- Dashboard
- Access Management
  - User groups
  - Users
  - Roles
  - Policies
  - Identity providers
  - Account settings
  - Root access management
  - Temporary delegation requests New

No MFA devices. Assign an MFA device to improve the security of your AWS environment.

Assign MFA device

Access keys (1)

Actions | Create access key

Use access keys to send programmatic calls to AWS from the AWS CLI, AWS Tools for PowerShell, AWS SDKs, or direct AWS API calls. You can have a maximum of two access keys (active or inactive) at a time. Learn more

Access key ID	Created on	Access key last used	Region last used	Service last used	Status
AKIA6ME7MP2STZV6V2OW	11 days ago	11 days ago	us-east-1	ec2	Active

CloudFront key pairs (0)

Actions | Upload | Create CloudFront key pair

You use key pairs in Amazon CloudFront to create signed URLs. You can have a maximum of two CloudFront key pairs (active or inactive) at a time.

Creation time	CloudFront key ID	Status

No CloudFront key pairs

```
[root@ip-172-31-75-220 ~]# aws s3 ls
[root@ip-172-31-75-220 ~]#
```

i-048ada3c159b1a20b (dockerhost)

PublicIPs: 100.56.11.136 PrivateIPs: 172.31.75.220

```
t@ip-172-31-75-220 ~]# aws s3 ls
t@ip-172-31-75-220 ~]# aws configure
Access Key ID [****************IGSD]: AWS Secret Access Key [****************8mmh]: Default region name [None]: us-east-1
ult output format [json]: json
t@ip-172-31-75-220 ~]# aws ecr get-login-password --region us-east-1 | docker login --username AWS --password-stdin 988176744101.dkr.
aws.com
ING! Your password will be stored unencrypted in /root/.docker/config.json.
igure a credential helper to remove this warning. See
s://docs.docker.com/engine/reference/commandline/login/#credentials-store

n Succeeded
t@ip-172-31-75-220 ~]#
```

macOS / Linux | Windows

Make sure that you have the latest version of the AWS CLI and Docker installed. For more information, see Getting Started with Amazon ECR.

Use the following steps to authenticate and push an image to your repository. For additional registry authentication methods, including the Amazon ECR credential helper, see Registry Authentication.

Code copied

1. ication token and authenticate your Docker client to your registry. Use the AWS CLI:

```
aws ecr get-login-password --region us-east-1 | docker login --username AWS --password-stdin 988176744101.dk
r.ecr.us-east-1.amazonaws.com
```

Note: If you receive an error using the AWS CLI, make sure that you have the latest version of the AWS CLI and Docker installed.

2. Build your Docker image using the following command. For information on building a Docker file from scratch see the instructions here. You can skip this step if your image is already built:

```
docker build -t testecr .
```

3. After the build completes, tag your image so you can push the image to this repository:

```
docker tag testecr:latest 988176744101.dkr.ecr.us-east-1.amazonaws.com/testecr:latest
```

4. Run the following command to push this image to your newly created AWS repository:

```
docker push 988176744101.dkr.ecr.us-east-1.amazonaws.com/testecr:latest
```

Close

```
[root@ip-172-31-75-220 ~]# aws s3 ls
[root@ip-172-31-75-220 ~]# aws configure
AWS Access Key ID [****************IGSD]: AWS Secret Access Key [****************8mmh]: Default region name [None]: us-east-1
Default output format [json]: json
[root@ip-172-31-75-220 ~]# aws ecr get-login-password --region us-east-1 | docker login --username AWS --password-stdin 988176744
azonaws.com
WARNING! Your password will be stored unencrypted in /root/.docker/config.json.
Configure a credential helper to remove this warning. See
https://docs.docker.com/engine/reference/commandline/login/#credentials-store

Login Succeeded
[root@ip-172-31-75-220 ~]# docker tag cusimage2:latest 988176744101.dkr.ecr.us-east-1.amazonaws.com/testecr:latest
[root@ip-172-31-75-220 ~]#
```

```
root@ip-172-31-75-220 ~]# docker images
EPOSITORY                                          TAG       IMAGE ID       CREATED             SIZE
usimage2                                           latest    99b33774ea8a   About an hour ago   117MB
88176744101.dkr.ecr.us-east-1.amazonaws.com/testecr   latest    99b33774ea8a   About an hour ago   117MB
root@ip-172-31-75-220 ~]#
```


Make sure that you have the latest version of the AWS CLI and Docker installed. For more information, see Getting Started with Amazon ECR.
Use the following steps to authenticate and push an image to your repository. For additional registry authentication methods, including the Amazon ECR credential helper, see Registry Authentication.
1. Retrieve an authentication token and authenticate your Docker client to your registry. Use the AWS CLI:
aws ecr get-login-password --region us-east-1 | docker login --username AWS --password-stdin 988176744101.dkr.ecr.us-east-1.amazonaws.com
Note: If you receive an error using the AWS CLI, make sure that you have the latest version of the AWS CLI and Docker installed.
2. Build your Docker image using the following command. For information on building a Docker file from scratch see the instructions here. You can skip this step if your image is already built:
docker build -t testecr .
3. After the build completes, tag your image so you can push the image to this repository:
docker tag testecr:latest 988176744101.dkr.ecr.us-east-1.amazonaws.com/testecr:latest
4. Run the following command to push this image to your newly created AWS repository:
docker push 988176744101.dkr.ecr.us-east-1.amazonaws.com/testecr:latest

---------- X ----------

Amazon Elastic Container Service
Express Mode
Clusters
Namespaces
Task definitions
Account settings
Amazon ECR
Repositories
AWS Batch
Online learning workshop
Documentation
Containers
Amazon Elastic Container Service
Fully managed containers
Amazon Elastic Container Service (Amazon ECS) is a highly scalable and fast container management service that makes it easy to run, stop, and manage containers on a cluster.
Deploy your containerized applications
Amazon ECS makes it easy to deploy, and scale Docker containers running applications, services, and batch proc
Get started
Pricing (US)
Amazon ECS on AWS Fargate
Amazon ECS Managed Instances
How it works
Console Mobile App
© 2026, Amazon Web Services, Inc. or its affiliates.
Privacy


Amazon Elastic Container Service > Clusters
Amazon Elastic Container Service
Express Mode
Clusters
Namespaces
Task definitions
Account settings
Amazon ECR
Repositories
AWS Batch
Online learning workshop
Documentation
Clusters (0) Info
Last updated
March 10, 2026, 12:13 (UTC+5:30)
Search clusters
By default, we only load up to 1,000 clusters at a time.
Cluster
Services
Tasks
Container instances
No clusters
Create cluster


Container instance Amazon Machine Image (AMI)
Choose the Amazon ECS-optimized AMI for your instance.
Amazon Linux 2023
EC2 instance type
Choose based on the workloads you plan to run on this cluster.
c7i-flex.large
x86_64
2 vCPU 4 GiB Memory
EC2 instance role
An instance role is used by Amazon EC2 instances to make AWS API requests. If you don't already have an instanc
Create default role
Create new instance pr

Provisioning model
Select a provisioning model for your instances

On-demand
With on-demand instances, you pay for compute capacity by the hour, with no long-term commitments or upfront payments.

Spot
Amazon EC2 Spot instances let you take advantage of unused EC2 capacity in the AWS cloud. Learn more

Container instance Amazon Machine Image (AMI)
Choose the Amazon ECS-optimized AMI for your instance.

Amazon Linux 2023

EC2 instance type
Choose based on the workloads you plan to run on this cluster.

t3.micro
x86_64
2 vCPU 1 GiB Memory

EC2 instance role
An instance role is used by Amazon EC2 instances to make AWS API requests. If you don't already have an instance IAM

Create default role

Create new instance profile

Create cluster

Choose the Amazon ECS-optimized AMI for your instance.

Amazon Linux 2023

EC2 instance type
Choose based on the workloads you plan to run on this cluster.

t3.micro
x86_64
2 vCPU 1 GiB Memory

EC2 instance role
An instance role is used by Amazon EC2 instances to make AWS API requests. If you don't already have an instance IAM

Create default role

Create new instance profile

Desired capacity
Specify the number of instances to launch in your cluster.

Minimum 0

Maximum 5

SSH Key pair
If you do not specify a key pair, you can't connect to the instances via SSH unless you choose an AMI that is configured

None - unable to SSH

Create a new key pair

Policy name	Type	Description
AmazonEC2ContainerServiceforEC2Role	AWS managed	Default policy for the Amazon EC2 Rol...

Create cluster

us-east-1f 172.31.64.0/20

us-east-1e 172.31.48.0/20

subnet-00bf5ce055fa47866 us-east-1d 172.31.32.0/20

subnet-0b36055e3d9bfde15 us-east-1a 172.31.0.0/20

Security group Info

Choose an existing security group or create a new security group.

- (●) Use an existing security group
- ( ) Create a new security group

Security group name

Choose an existing security group.

Choose security groups

sg-091ba32f5d21ac026
default

Auto-assign public IP Info

Choose whether to auto-assign a public IP to the Amazon EC2 instances

Use subnet setting

Clusters (1) Info

Last updated
March 10, 2026, 12:43 (UTC+5:30)

Search clusters

By default, we only load up to 1,000 clusters at a time.

Cluster	Services	Tasks	Container instances	CloudWatch r
testecs	0	No tasks running	1 EC2	Default

EC2 > Instances

:2

ıshboard
VS Global View
ents
stances
stances
stance Types
unch Templates
ot Requests
vings Plans
served Instances
dicated Hosts
pacity Reservations
pacity Manager New
ıages
Mls

Instances (1/2) Info

Connect | Instance state | Actions | La

Find Instance by attribute or tag (case-sensitive)

All states

Instance state = running | Clear filters

Name	Instance ID	Instance state	Instance type	Status check	Alarm status
dockerhost	i-048ada3c159b1a20b	Running	t3.micro	3/3 checks passec	View alarms
ECS Instance - ...	i-0d941ee8613b6928e	Running	t3.micro	Initializing	View alarms

i-0d941ee8613b6928e (ECS Instance - testecs)

Details | Status and alarms | Monitoring | Security | Networking | Storage | Tags

Instance summary Info

Instance ID
i-0d941ee8613b6928e

Public IPv4 address
44.200.30.186 | open address

Private IPv4 addresses
172.31.70.32

IPv6 address

Instance state

Public DNS


EC2 > Instances
EC2
Dashboard
AWS Global View
Events
Instances
Instances
Instance Types
Launch Templates
Spot Requests
Savings Plans
Reserved Instances
Dedicated Hosts
Capacity Reservations
Capacity Manager New
Images
Instances (1/2) Info
Connect
Instance state
Actions
Name
dockerhost
ECS Instance
i-048ada3c159b1
Details
Instance summa
Instance ID
Terminate (delete) instance
On an EBS-backed instance, the default action is for the root EBS volume to be deleted when the instance is terminated. Storage on any local drives will be lost.
Are you sure you want to terminate these instances?
Instance ID
Termination protection
i-048ada3c159b1a20b (dockerhost)
Disabled
To confirm that you want to delete the instances, choose the terminate button below. Instances with termination protection enabled will not be terminated. Terminating the instance cannot be undone.
Skip OS shutdown
This option skips the graceful OS shutdown process. Use only when your instance must be stopped immediately, such as during an emergency or failover.
Skip OS shutdown
Cancel
Terminate (delete)